

Spool Admin User Guide

Version V6R1M0 2010

Table of Contents

Introduction	6
Why Choose CoolSpools Spool Admin?	7
What's new in this release?	7
What was new in Version 2 of CoolTools?	8
Prerequisites	9
Upgrade Notes	10
License Keys	
Warning/Disclaimer	
Minimum OS/400 Release Level	11
Product Library	11
Memo to Users	
If you are migrating from Version 1 of CoolTools	
Installation	14
Maintenance	15
Using CoolSpools Spool Admin	16
Concepts	
Spooled File Monitors	
Spooled File Rules	
Spooled File Scripts	
Spooled File Transactions	
Transaction Rule Steps	
Authorities	19
The CoolSpools Spool Admin Menu	
WRKSPLFPDM (Work with Spooled Files PDM-style)	
Working with Spooled Files in Interactive Mode	
Options	
Standard options	
User-defined options	34
Function keys	
Working with Spooled Files in Batch Mode	
IMPADMDTA command	
WRKSTDOPT (Work with Standard Options)	

Options	39
Function keys	39
Attributes	41
Function keys	42
WRKUSROPT (Work with User Options)	43
Options	43
Function keys	44
Attributes	45
Setting up CoolSpools Spool Admin to process spooled files automatical	ly47
Using the Wizard	47
Manual Setup	47
Create spooled file monitors	47
Create spooled file scripts	47
Create spooled file rules	48
Start Spooled File Monitoring	48
Checking Spooled File Processing	48
Resolving errors	48
WRKSPLMON (Work with Spooled File Monitors)	49
Options	49
Function keys	50
Attributes	50
Other commands for working with spooled file monitors	51
CRTSPLMON (Create Spooled File Monitor)	51
CHGSPLMON (Change Spooled File Monitor)	51
CPYSPLMON (Copy Spooled File Monitor)	51
DLTSPLMON (Delete Spooled File Monitor)	52
WRKSPLSCP (Work with Spooled File Scripts)	53
Options	54
Function keys	54
Attributes	54
Other commands for working with scripts	54
CRTSPLSCP (Create Spooled File Script)	54
CHGSPLSCP (Change Spooled File Script)	54
CPYSPLSCP (Copy Spooled File Script)	55
DLTSPLSCP (Delete Spooled File Script)	55

WRKSPLSCPE (Work with Spooled File Script Entries)	56
Options	57
Function keys	57
Parameters	57
Other commands for working with script entries	59
ADDSPLSCPE (Add Spooled File Script Entry)	59
CHGSPLSCPE (Change Spooled File Script Entry)	59
CPYSPLSCPE (Copy Spooled File Script Entry)	59
RMVSPLSCPE (Remove Spooled File Script Entry)	60
WRKSPLRUL (Work with Spooled File Rules)	61
Options	62
Function keys	62
Parameters	62
Other commands for working with rules	66
CRTSPLRUL (Create Spooled File Rule)	66
CHGSPLRUL (Change Spooled File Rule)	67
CPYSPLRUL (Copy Spooled File Rule)	67
DLTSPLRUL (Delete Spooled File Rule)	67
CoolSpools Spool Admin Jobs	68
Work Management	68
Jobs	68
STRMONSPLF (Start Monitoring Spooled Files)	70
Parameters	70
ENDMONSPLF (End Monitoring Spooled Files)	71
STRPRCJOB (Start Processing Jobs)	71
Parameters	71
ENDPRCJOB (End Processing Jobs)	72
Parameters	72
WRKSPLTRN (Work with Spooled File Transactions)	73
Deremetere	73
Parameters	74
Options	
Options	75
Options Function keys	75 75
Options Function keys Positioners	75 75 76

Other commands for working with transactions	81
CRTSPLTRN (Create Spooled File Transaction)	31
Parameters	31
DLTSPLTRN (Delete Spooled File Transaction)	33
Parameters	33
WRKTRNSTS (Work with Transaction Status)	85
Function keys	35
Data	36
Substitution variables	88
CoolSpools Spool Admin Log File	90

Introduction

CoolSpools Spool Admin (previously known as "CoolTools") provides spooled file management and distribution functionality for the CoolSpools suite of programs.

CoolSpools Spool Admin provides:

- The ability to create **spooled file monitors**, which are processes which detect the arrival of spooled files on specified output queues in a ready status and then carry out user-defined actions against those spooled files.
- The facility to define **spooled file rules** which determine what actions are applied to which spooled files.
- The means to specify **spooled file scripts** which determine a sequence of operations to be applied to a spooled file.
- WRKSPLFPDM (Work with Spooled Files PDM-style), a command which provides a simple and familiar but powerful and flexible way of operating on sets of selected spooled files. When run interactively, WRKSPLFPDM is similar to the PDM commands WRKLIBPDM, WRKOBJPDM and WRKMBRPDM, but whereas those commands allow you to work with libraries, objects and members respectively, WRKSPLFPDM provides the equivalent functionality in relation to spooled files.
- **RUNSPLFCMD** (Run Spooled File Commands), a command which provides similar functionality to WRKSPLFPDM, but without a user interface
- The ability to customize the standard options provided by WRKSPLFPDM and RUNSPLFCMD (i.e. you can determine what command string is run when, for example, a user selects option 10 against a spooled file).
- Control over authority to options and command parameters within WRKSPLFPDM. For example, you can manage user authorities to each individual CoolSpools Spool Admin user-defined option and standard options.

CoolSpools Spool Admin dovetails with **CoolSpools Spool Converter** which converts spooled files to stream files in a variety of formats such as PDF and Excel. With **CoolSpools Spool Admin** and **CoolSpools Spool Converter** together, it's easy to create electronic documents from multiple spooled files automatically. If you also have **CoolSpools Email**, you can email them too!

Why Choose CoolSpools Spool Admin?

Let's look at some possible uses for CoolSpools Spool Admin.

If you've got *CoolSpools Spool Converter*, you'll know how much your company can save in time and money and effort by replacing paper with electronic documents such as PDFs. Maybe you're now converting your business reports to PDF format every night rather than printing them so they can be emailed to your users or customers or published on your website or intranet.

With CoolSpools Spool Admin , you can make this even easier by detecting every time a spooled file is created on a given output queue and automatically applying one or more actions to that spooled file.

But what about the hundreds or even thousands of archived spooled files you've accumulated over previous years and which you'd now like to convert?

CoolSpools Spool Admin can help you here too.

Using the various criteria available, you can easily use WRKSPLFPDM or RUNSPLFCMD to select sets of related spooled files to work with and convert them all to PDF format in a single batch job.

Or maybe you'd like a way of saving your spooled files every night so they don't have to be kept online all the time and clutter up your disk? With WRKSPLFPDM and *CoolSpools Spool Converter* you can easily save an entire output queue in *CoolSpools Spool Converter's* highly compressed archive stream file format by running a single command. These archives can then be backed off to tape or even burnt to CD using a cheap and simple CD writer on an attached PC. If you need them back later, you just load them off the CD on to the system i using FTP or a network drive and restore them.

Or perhaps you're just looking for an even better way to manage your spooled files online than WRKSPLF? With WRKSPLFPDM you can:

- Select spooled files by spooled file name
- Select spooled files by output queue
- Select spooled files created between a range of dates
- Repeat options PDM-style using F13
- Apply PDM-style user-defined options to sets of selected spooled files
- Use substitution variables in user-defined options

What's new in this release?

- New Automatic spooled file processing setup wizard
 - > Simplifies setting automatic processing of spooled files
 - Guides you through the steps required and prompts for selection of output queues to watch, spooled files to select and actions to perform
 - Available from SPOOLADMIN menu option 20, CFGSPLMON command or WRKSPLFPDM option 34.
- Integration with CoolSpools Spool Converter enhancements

CoolSpools Spool Admin has been updated with several new standard options that take advantage of new features within CoolSpools Spool Converter:

CoolSpools Spool Admin User Guide V6R1 www.ariadnesoftware.co.uk

- > 18=Convert to XML
- > 19=Convert to Excel using a map
- 28= Email spooled file as XML
- > 29= Email spooled file as Excel using a map
- > 31=Send spooled file using TCP/IP (LPR)
- 32=View spooled file text (allows displaying of spooled files that DSPSPLF can't handle e.g. *USERASCII)
- > 33=Design report definition

What was new in Version 2 of CoolTools?

Highlights of Version 2 of CoolTools included:

- Extension of the number of available WRKSPLFPDM options from 12 to 99.
- The ability to customize WRKSPLFPDM standard options 01-99 at the system-level or for individual users. This replaces the facility previously available in V1 to define system and user defaults.
- Greatly enhanced control over user capabilities and option security, using registered functions. It is now possible to control who has access to what system features at the level of individual users and groups. These features cover standard WRKSPLFPDM options, user-defined options, CoolSpools parameters and other aspects as well. These new features replace the capabilities by user class that were definable in V1.
- New options for setting up automatic processing of spooled files. As soon as a spooled file is created on a particular output queue with a status of "ready", it can be detected and processed. What processing should be performed can be specified for each type of spooled file by defining **spooled file rules**.
- **Spooled file scripts** to allowing the definition of a simple sequential list of actions to be performed on a spooled file.
- New WRKSPLFPDM options for selecting spooled files by: spooled file number; age range in days; status; spooled file type.
- Discontinuation of support for user-defined options defined in a PDM options file. All user-defined options must be defined using the WRKUSROPT function.
- Withdrawal of support for WRKSYSCTL. The functions previously provided by WRKSYSCTL are now available from WRKSTDOPT and/or WRKREGFNC.

Prerequisites

OS/400 V5R3M0 or higher.

20 Mb of system i disk space.

For spooled file conversion: For email options: CoolSpools Spool Converter CoolSpools Email

Upgrade Notes

Please read the following notes carefully before upgrading to CoolSpools Spool Admin V6R1M0 from an earlier version of CoolTools, CoolSpools Spool Admin or CoolSpools PLUS.

CoolSpools Spool Admin was previously available as both a standalone module called CoolTools and also as part of the complete CoolSpools PLUS suite. Now, CoolSpools Spool Admin is packaged as a product option (option 3) of CoolSpools V6R1M0.

To determine which version of CoolSpools PLUS or CoolTools you are running, check the name of the library in which the SNDCMNMSG command object you are using resides, e.g.:

DSPOBJD OBJ(WRKSPLFPDM) OBJTYPE(*CMD)

The library name corresponds to the product and version shown in the table below:

Product Library Name	Licensed Program Id	Version
SPLTLSV1R1	1SPLTLS	CoolTools Version 1
SPLTLSV2R1	2SPLTLS	CoolTools Version 2
COOLSPV5R1	5COOLSP	CoolSpools PLUS V5R1M0

If your command is in a library other than those shown, you are either running an unsupported, unlicensed version or have moved or copied the command object from its original location. Contact support@ariadnesoftware.co.uk for assistance.

<u>License Keys</u>

You are entitled to upgrade to V6R1M0 of CoolSpools Spool Admin free of charge if:

• the machine on which you wish to run CoolSpools Spool Admin V6R1M0 has a valid license for an earlier version of CoolTools or CoolSpools PLUS

and

• you are either in your first 12 months' maintenance period after purchase or have paid your latest annual maintenance invoice.

If you wish to upgrade, you can simply download the software from <u>www.ariadnesoftware.co.uk</u> and install it according to the instructions contained in the "Installation" section of this User Guide. However, if you licensed an earlier version of CoolTools or CoolSpools PLUS, you will need to request a license key for the new version. Simply e-mail <u>support@ariadnesoftware.co.uk</u> and ask for your key for V6R1M0 of CoolSpools Spool Admin. Please quote your system serial number(s) and processor group code(s) in your e-mail. These are shown at the top of the WRKLICINF screen.

CoolSpools Spool Admin User Guide V6R1

Without a license key, CoolSpools Spool Admin V6R1M0 will allow you a 30-day grace period and will then no longer run.

If you have not paid your annual maintenance invoice, and if you need longer than 30 days to test CoolSpools Spool Admin V6R1M0, we will, on request, send you a temporary license key to extend the trial period.

If you require additional temporary license keys to assist with testing CoolSpools Spool Admin V6R1M0, or if you run into any problems during your testing, please do not hesitate to contact us at support@ariadnesoftware.co.uk.

Warning/Disclaimer

We recommend strongly that all production applications are re-tested thoroughly using the new version in your development environment before you switch over to running the new version in your production environment.

All CoolSpools versions are packaged as separate licensed programs and install into different libraries. This means that all versions of CoolSpools can coexist and run alongside one another on the same machine. You can switch an application from using one version to using another simply by changing the library list of the job to include the appropriate version library or by specifying a different library name when you run the command. Hence it is guite a simple matter to test your applications using the new version while continuing to run the older version in production.

Please note that while ariadne makes every effort to ensure that CoolSpools functions in the same way with the same parameters from one version to the next, it is not possible to guarantee this. This is why you should re-test your applications against a new version before going live with it as it is possible that in some cases different parameter settings will be necessary to obtain the same results as before.

ariadne software accepts no responsibility for any damage, expense or loss of income incurred as a result of unforeseen and unwanted effects resulting from installing new versions of its software or applying PTFs.

Minimum OS/400 Release Level

The minimum OS/400 release level required to run V6R1M0 of CoolSpools Spool Converter is OS/400 V5R3M0.

If you are running OS/400 V5R2M0 or an earlier version of OS400, you will not be able to install V6R1M0 of CoolSpools Spool Admin.

Product Library

All product options of CoolSpools V6R1M0 install into the single product library COOLSPV6R1. This means that you no longer have to manage multiple product libraries for the separate modules that made up CoolSpools PLUS V5R1M0 (CoolSpools Database, CoolSpools Email, CoolSpools Spool Converter etc.)

You will probably need to change library lists in job descriptions and other system objects in order to pick up the new version of the code rather than the old.

This change of library name has the advantage that it allows you to run both V6R1M0 and the earlier versions on the same machine. You are therefore able to test V6R1M0 before

CoolSpools Spool Admin User Guide V6R1

swapping your production applications over to the new version, as we strongly advise you to do.

Memo to Users

Please refer to the <u>Memo to Users</u> for important information about changes you need to take account of before migrating to CoolSpools Spool Admin from an earlier version of CoolTools or CoolSpools PLUS.

If you are migrating from Version 1 of CoolTools

WRKSPLFPDM standard options

The default standard WRKSPLFPDM option numbers, and command strings that underlie them, have both changed.

However, since CoolSpools Spool Admin now gives you total control over the definition and availability of these options, allowing you to customize them as you wish:

- You can use the WRKSTDOPT command to modify the system-supplied option descriptions and command strings, or to define new options;
- This can be done either at system-level, or for each individual user;
- You can use the WRKREGFNC command to define who has access to which options

If you decide to use the options as supplied with V2 of CoolSpools Spool Admin, you should warn your users that the options have changed. Alternatively, review the options as supplied and amend as appropriate to your environment.

WRKSPLFPDM user-defined options

V2 does not support the use of user-defined options specified in a PDM options file. This has proved necessary in order to allow enhancement of this area of the system, e.g. the use of registered functions to control access to user-defined functions.

A utility (CVTPDMOPT) is supplied to facilitate the conversion of options defined in a PDM options file to CoolSpools Spool Admin user-defined options so they can be used with V2.

WRKSYSCTL (Work with System Controls)

V2 does not support the use of the WRKSYSCTL (Work with System Controls) command. Its functions are provided, in a much enhanced way, by the WRKSTDOPT and WRKREGFNC commands:

- The "Capabilities by User Class" feature is replaced by the use of registered functions (defined with WRKREGFNC) which allow control over the use of WRKSPLFPDM standard and user-defined options, and CoolSpools parameters, at the level of individual users and groups.
- CoolSpools parameter defaults are definable separately for each individual WRKSPLFPDM standard option through the use of the WRKSTDOPT command.

The command string underlying each standard option can be defined at a system level or by individual user.

A conversion utility (CVTAUT) is provided to allow you to set up Version 2 authorities based on the way your capabilities by user class were defined in Version 1.

Users with Limited Capabilities

Version 1 of CoolTools prevented users with LMTCPB(*YES) specified for their user profile from running commands on the WRKSPLFPDM command line.

In Version 2, you can manage authority to the ARIADNE_ALW_LMTCPB_CMD registered function to determine whether a user with LMTCPB(*YES) can run any commands from the WRKSPLFPDM command line.

If a user is not authorized to this function, and the user has LMTCPB(*YES) specified on their user profile, the user will not be able to run any commands from the WRKSPLFPDM command line (as per Version 1).

However, if a user is authorized to this function, and the user has LMTCPB(*YES) specified on their user profile, the user will be able to run commands from the WRKSPLFPDM command line, but only those commands with ALWLMTUSR(*YES) specified.

Installation

Refer to the Installation Guide for instructions.

Maintenance

Refer to the Maintenance Guide for instructions.

Using CoolSpools Spool Admin

<u>Concepts</u>

Before you can configure CoolSpools Spool Admin to process spooled files automatically, it is necessary to understand some concepts upon which the design of CoolSpools Spool Admin is based.

Spooled File Monitors

A **spooled file monitor** is a job which monitors for the arrival of spooled files in a ready status on one or more specified output queues. The spooled file monitor is thus the mechanism whereby CoolSpools Spool Admin detects spooled files that it needs to process.

Technically, spooled file monitors rely upon a feature of AS/400 output queues which allow you to associate a data queue with an output queue. If an output queue has a data queue associated with it, every time a spooled file arrives on that output queue in a ready status, a message is sent to the associated data queue. The CoolSpools Spool Admin spooled file monitor reads messages from the data queue as they are created and can thus detect spooled files that need to be processed very quickly and with very little load on the system.

It is important to note that messages are sent to the data queue only in respect of spooled files that have a status of RDY (Ready). If the spooled file is created with a status of HLD (Held), no message is sent to the data queue and the spooled file monitor job will not detect the new spooled file.

This provides a means whereby you can easily manage which spooled files are processed by CoolSpools Spool Admin and which are not. However, if you have existing applications which create spooled files in a "Held" status, and you wish to have CoolSpools Spool Admin process those spooled files automatically, you will need to change the application to create them in a "Ready" status instead, for example by changing printer files from HOLD(*YES) to HOLD(*NO).

Alternatively, rather than using a spooled file monitor to process spooled files automatically as they are created, you could run WRKSPLFPDM or RUNSPLFCMD periodically to process batches of spooled files with a "Held" status.

Spooled File Rules

Once a spooled file monitor job has detected that a spooled file has been created, CoolSpools Spool Admin needs to know what to do with it. You tell it what to do with different types of spooled files by defining **spooled file rules**.

A spooled file rule basically consists of:

- A set of **criteria** which are compared with the spooled file's attributes and determine whether the rule is selected or not
- An **action** to be performed against the spooled file when the spooled file matches the criteria and is selected to be processed

The action to be performed can be one of the following:

CoolSpools Spool Admin User Guide V6R1 www.ariadnesoftware.co.uk

- Run a standard option. These are similar to the standard options available from the WRKSPLFPDM and RUNSPLFCMD commands and cover the basic spooled file operations such as *HLD (Hold the spooled file), *RLS (Release the spooled file) and *DLT (Delete the spooled file), as well as those that require other ariadne products to be installed such as converting the spooled file to PDF, Excel etc. using CoolSpools or emailing it using CoolSpools and CoolSpools Email.
- Run a user-defined option. User-defined options are defined using the WRKUSROPT command. The user-defined option can include substitution variables which are replaced at run time with the actual corresponding spooled file attributes, e.g. &J is replaced with the name of the job which created the spooled file.
- **Run a command.** You can specify a single ad hoc command to be run against the spooled file in question. Again, substitution variables are supported.
- **Run a script.** You can run a CoolSpools Spool Admin spooled file script against the spooled file (see below).

Spooled File Scripts

A **spooled file script** provides a way of specifying a group of actions which will occur together in specified sequence. Each individual action is defined as a **spooled file script entry** which can be:

- a standard spooled file option
- a user-defined option
- a command string
- a call to another script.

Each spooled file script consists of between zero or more script entries (maximum 9,999).

Spooled File Transactions

A data queue is a volatile storage area. It has the great advantage that data can be written to and read from a data queue very quickly and with minimal system overhead. However, once an entry has been removed from a data queue, it has been lost permanently and cannot be recovered.

In order to provide a robust and reliable system for managing spooled file, CoolSpools Spool Admin therefore uses a combination of data queues and database files. Data queues are used to notify processes of events that have occurred (such as the creation of a new spooled file) in an efficient manner. However, as soon as a process has been notified of an event, it will save the information it has received in a database file in order to ensure that this information is not lost, and that it can be managed subsequently.

One example of this is the creation of **spooled file transactions**. Each time a new spooled file is created and detected by a spooled file monitor, the monitor will create a spooled file transaction record in a database file. This spooled file transaction record can then be used to manage the operations that are required to be applied to the spooled file subsequently.

Transaction Rule Steps

Each spooled file transaction will be analyzed by CoolSpools Spool Admin according to the spooled file rules that have been defined. Where the spooled file in question matches the criteria for a rule, CoolSpools Spool Admin will select the rule and will perform the corresponding action or actions that the rule defines on the spooled file. Each action to be performed against a spooled file as a result of a spooled file rule having been selected in relation to a spooled file transaction is called a **transaction rule step**.

Authorities

This system of authorities is based upon the concept of *user function registration* which is a feature of the system i operating system (see

<u>http://publib.boulder.ibm.com/infocenter/system i/v5r3/index.jsp</u>) and is thus highly secure. User authority to registered functions are stored securely as part of the system i user profile and can be saved and restored like other system i authorities.

CoolSpools Spool Admin uses these features to determine which users are able to:

- run WRKSPLFPDM standard options (e.g. who can select option 4=Delete against a spooled file)
- run WRKSPLFPDM user-defined options (e.g. if you define an option MV to move a spooled file to a different output queue, who can run that option)
- use the various parameters of the different CoolSpools' commands (e.g. whether a particular user can modify the default value of the FROMEMAIL parameter of the CVTSPLPDF command)
- select certain specially controlled CoolSpools features (e.g. the "Delete after sending" option of the EMAILOPT parameter).

Each of these features will be identified by means of a named registered function. Authority to particular features can then be set at the level of:

- "Default" (*PUBLIC) authority
- Group profile authority
- Individual user authority

CoolSpools Spool Admin WRKREGFNC (Work with Registered Functions) command provides a convenient means of managing these CoolSpools Spool Admin authorities, although it is also possible to manage them through the IBM-supplied commands and APIs, if preferred (e.g. WRKFCNUSG).

The CoolSpools Spool Admin Menu

The CoolSpools Spool Admin menu is the simplest starting point for working with CoolSpools Spool Admin commands.

You display the CoolSpools Spool Admin menu by entering this command:

GO COOLSPV6R1/S	POOLADMIN
SPOOLADMIN CoolSpools - Spooled	File Admin Menu
Select one of the following:	
1. Work with spooled files	2. Process spooled files in batch
11. Work with std. options (system) 12. Work with user options	13. Work with std. options (user)
21. Work with spooled file monitors 22. Work with spooled file scripts	23. Work with spooled file rules
31. Start monitoring spooled files	32. End monitoring spooled files
41. Unprocessed splf transactions	43. All splf transactions
42. Splf transactions in error	44. Work with transaction status
Selection or command	
===>	
F3=Exit F4=Prompt F9=Retrieve F12=Car	ncel
F13=Information Assistant F16=AS/400 main	menu

The options available from this menu are as follows:

1 Work with spooled files.

This option runs the WRKSPLFPDM command. It provides an online facility for selecting and managing spooled files.

2 Process spooled files in batch

This option will prompt the submission of a job to run the RUNSPLFCMD command. It allows you to run a job to perform spooled file operations in batch.

11 Work with std. options (system)

This is equivalent to running WRKSTDOPT USER(*SYSDFT). It enables you to customize the default system standard options 1-12 available in WRKSPLFPDM and RUNSPLFCMD.

This command is intended to be an administrator function and is shipped with public *EXCLUDE authority. You will need to be signed on as a user with *ALLOBJ authority, or be granted authority by your security officer, in order to run this option.

Also, in order to run WRKSTDOPT to customize the system default standard options, you must have authority to function ARIADNE_STD_OPT_SYS_DFT_CHG (see "Authorities" earlier in this User Guide).

12 Work with user options

This is equivalent to running WRKUSROPT. It lets you work with CoolSpools Spool Admin user-defined options.

This command is intended to be an administrator function and is shipped with public *EXCLUDE authority. You will need to be signed on as a user with *ALLOBJ authority, or be granted authority by your security officer, in order to run this option.

13 Work with std. options (user)

This is equivalent to running WRKSTDOPT for a user other than *SYSDFT. It enables you to customize the default system standard options 1-12 available in WRKSPLFPDM and RUNSPLFCMD for a particular user (by default, the current user).

This command is intended to be an administrator function and is shipped with public *EXCLUDE authority. You will need to be signed on as a user with *ALLOBJ authority, or be granted authority by your security officer, in order to run this option.

Also, in order to run WRKSTDOPT to customize the standard options for a user other than yourself, you must have authority to function ARIADNE_STD_OPT_OTH_USR_CHG (see "Authorities" earlier in this User Guide).

21 Work with spooled file monitors

This is equivalent to running WRKSPLMON. It provides a facility for managing spooled file monitors.

This command is intended to be an administrator function and is shipped with public *EXCLUDE authority. You will need to be signed on as a user with *ALLOBJ authority, or be granted authority by your security officer, in order to run this option.

22 Work with spooled file scripts

This is equivalent to running WRKSPLSCP. This is where you create, change and delete spooled file scripts and their entries.

This command is intended to be an administrator function and is shipped with public *EXCLUDE authority. You will need to be signed on as a user with *ALLOBJ authority, or be granted authority by your security officer, in order to run this option.

23 Work with spooled file rules

This is equivalent to running WRKSPLRUL. This lets you manage spooled file rules.

This command is intended to be an administrator function and is shipped with public *EXCLUDE authority. You will need to be signed on as a user with *ALLOBJ authority, or be granted authority by your security officer, in order to run this option.

31. Start monitoring spooled files

This is equivalent to running STRMONSPLF. It starts a set of jobs which monitor and process spooled files.

32. End monitoring spooled files

This is equivalent to running ENDMONSPLF. It ends the jobs started by the previous option.

41. Unprocessed splf transactions

This is equivalent to running WRKSPLTRN OPTION(*UNPRC). It shows you a list of spooled file transactions which have not yet been processed.

42. Splf transactions in error

This is equivalent to running WRKSPLTRN OPTION(*ERROR). It shows you a list of spooled file transactions which are in error.

43. All spooled file transactions

This is equivalent to running WRKSPLTRN OPTION(*ERROR). It shows you a list of all spooled file transactions.

44. Work with transaction status

This is equivalent to running WRKTRNSTS. It displays a screen summarizing the current processing position and providing some basic statistics.

WRKSPLFPDM (Work with Spooled Files PDM-style)

The **WRKSPLFPDM** (Work with Spooled Files PDM-style) command lets you operate on sets of related spooled files interactively or in batch.

The first group of command parameters provides selection criteria you can use to define the spooled files you want to work with or process.

To run WRKSPLFPDM, enter this command:

COOLSPV6R1/WRKSPLFPDM

USER

The **USER** (User) parameter allows you to select spooled files based on the user profile of the user who created them.

Possible values are:

*CURRENT	(Default) Only files created by the user running this command are selected.
*ALL	Files created by all users are selected.
user-name	Specify a user name. Only files created by that user name are selected.

SPLFNAME

The **SPLFNAME** (Spooled File Name) parameter allows you to select spooled files by spooled file name.

Possible values are:

*ALL	(Default) Spooled files are selected irrespective of their name.
generic*-splf	Specify the generic name of the spooled files to be listed. A generic name is a character string that contains one or more characters followed by an asterisk (*).
splf-name	Specify a spooled file name. Only files with that spooled file name are selected.

PRTDEV

The **PRTDEV** (Printer device) parameter allows you to select spooled files based on the printer device with which they are associated.

Possible values are:

*ALL	(Default) Spooled files are selected irrespective of the printer device with which they are associated.
prtdev-name	Specify a printer device name. Only files on the device output queue for the specified printer device will be selected.

ουτα

The **OUTQ** (Output queue) parameter allows you to select spooled files based on the output queue with which they are associated. If a printer device output queue is specified, this is equivalent to specifying the printer device name on the previous parameter.

CoolSpools Spool Admin User Guide V6R1

Possible values are:

*ALL	(Default) Spooled files are selected irrespective of the output queue with which they are associated.
outq-name	Specify an output queue name. Only files on the output queue will be selected.

FORMTYPE

The **FORMTYPE** (Form type) parameter allows you to select spooled files based on their form type.

Possible values are:

*ALL	(Default) Spooled files are selected irrespective of their form type.
*STD	Only spooled files with the standard form type are selected.
form_type	Specify a form type. Only files with this form type will be selected.

USRDTA

The **USRDTA** (User Data) parameter allows you to select spooled files based on their user data attribute.

Possible values are:

*ALL	(Default) Spooled files are selected irrespective of their user data attribute.
user_data	Specify the user data attribute. Only files with this user data attribute will be selected.

JOB

The **JOB** (Job) parameter allows you to select spooled files based on the job with which they are associated.

Possible values are:

*ALL	(Default) Spooled files are selected irrespective of the job with which they are associated.
*	The current job. Only spooled files associated with the current job are selected.
qual-job-name	Enter a full qualified job name. Only spooled files associated with this job are selected.
*ANY	Can be used for the user id and job number components of the fully qualified job name to indicate that CoolSpools Spool Admin should select jobs based on the job name alone and ignore the user id and/or job number.

SPLNBR

The **SPLNBR** (Spooled File Number) parameter allows you to select spooled files based on their spooled file number.

CoolSpools Spool Admin User Guide V6R1

Possible values are:

*ALL	(Default) Spooled files are selected irrespective of their spooled file number.
spl_nbr	Specify the spooled file number. Only files with this spooled file number will be selected.

FROMDATE

The **FROMDATE** (From Date) parameter allows you to select spooled files based on their creation date.

Possible values are:

*EARLIEST	(Default) Spooled files are selected irrespective of how early their creation date is.
from_date	Specify the earliest creation date. Only files with a creation date equal to or after this date will be selected.

TODATE

The **TODATE** (To Date) parameter allows you to select spooled files based on their creation date.

Possible values are:

*LATEST	(Default) Spooled files are selected irrespective of how recent their creation date is.
to_date	Specify the latest creation date. Only files with a creation date equal or prior to this date will be selected.

AGERANGE

The **AGERANGE** (Age Range) parameter allows you to select spooled files based on their creation date, but, rather than entering specific dates on the FROMDATE and TODATE parameters, you may enter an age range in days. This is often more convenient for automated operations than specifying a date range.

Possible values are:

*ALL	(Default) Spooled files are selected irrespective of how long ago they were created.
*MIN	The value *MIN for the "from" element of the range indicates that there is no lower limit for the age range, i.e. that spooled files will be included so long as they are more recent than the upper limit.
*MAX	The value *MAX for the "to" element of the range indicates that there is no upper limit for the age range, i.e. that spooled files will be included so long as they are older than the lower limit.
age_range	Enter an age range in days. Spooled files are selected based on their creation date. If the current date minus the creation date falls in this range of days, the spooled file will be selected. The calculation of the number of days is

based on the date alone and takes no account of the time. For example, a spooled file created one minute before midnight on one day will be considered to be one day old if processed by CoolSpools Spool Admin one minute after midnight (i.e. only two minutes later).

STATUS

The **STATUS** (Spooled File Status) parameter lets you select spooled files based on their status.

Possible values are:

*ALL	(Default) Spooled files are selected irrespective of their status.
*READY	Spooled files are selected if their status is "ready".
*HELD	Spooled files are selected if their status is "held".
*SAVED	Spooled files are selected if their status is "saved".

The remaining parameters appear only if F9 or F10 is pressed when the command is prompted.

DEVTYPE

The **DEVTYPE** (Printer device type) parameter allows you to select spooled files based on their printer device type attribute.

Possible values are:

*ALL	(Default) Spooled files are selected irrespective of their printer device type attribute.
*SCS	Only *SCS spooled files are selected.
*IPDS	*IPDS spooled files.
*AFPDS	*AFPDS spooled files.
*AFPDSLINE	*AFPDSLINE spooled files.
*LINE	*LINE spooled files.
*USERASCII	*AFPDS spooled files.

MODE

The **MODE** (Run mode) parameter allows you to specify the mode in which WRKSPLFPDM runs.

Possible values are:

*JOBTYPE (Default) The run mode is determined by the type of job. If the job running the WRKSPLFPDM command is a batch job, WRKSPLFPDM runs in batch mode, otherwise it runs in interactive mode.

CoolSpools Spool Admin User Guide V6R1 www.ariadnesoftware.co.uk ***BATCH**

WRKSPLFPDM runs in batch mode. If the job running the WRKSPLFPDM command is an interactive job, WRKSPLFPDM runs as it would do if the job were a batch job, in other words the spooled file list is not displayed and the option supplied on the OPTION parameter is automatically applied to each spooled file selected.

OPTION

The **OPTION** (Batch processing option) parameter allows you to specify the option which will be processed against each selected spooled file when the command is run in batch.

This parameter is mandatory when the command is run in batch and is ignored if it is run interactively.

Possible values are:

*NONE	(Default) No option is specified. This is invalid if the command is submitted to batch. In batch mode, an option is required otherwise WRKSPLFPDM has nothing to do.
option	Specify either one of the standard options available when the command is run interactively, or a user-defined option.
	Refer to the section on the WRKSPLFPDM command above for a list of the standard options supplied with CoolSpools Spool Admin. These standard options may be customized using the WRKSTDOPT command.
	User-defined options are defined using the WRKUSROPT command and, like PDM user-defined options, can include substitution variables.
RM	

OPTPARM

The **OPTPARM** (Option parameters) parameter enables you to supply additional command parameters for use with the batch processing option specified on the **OPTION** parameter.

Possible values are:

*NONE	(Default) There are no additional parameters.
parameters	Specify additional parameters which will be used in addition to the basic parameters associated with the option defined on the OPTION parameter.

For example:

WRKSPLFPDM USER(*CURRENT) SPLFNAME(QPJOBLOG) **OPTION(3) OPTPARM(**'outq(joblogs)')

If run in batch mode, this command selects all spooled files for the current user called QPJOBLOG and runs option 2 (Change spooled file attributes) against each of them in

CoolSpools Spool Admin User Guide V6R1

turn. The attribute which is changed is specified on the **OPTPARM** parameter: the spooled files are moved to output queue **JOBLOGS**.

Substitution variables (see p88) may be used on this parameter, for example:

WRKSPLFPDM

... MODE(*BATCH) OPTION(20) OPTPARM('tostmf(&f.pdf) emailto((&m &e *PRI))')

All spooled files selected by this command will have option 20 (Send PDF) applied to each of them in turn. The stream file name will be the name of the spooled file (as denoted by substitution variable **&F**) with an extension of .PDF. The stream files will be emailed to the email address of the user who created the spooled file (as denoted by substitution variables **&M** and **&E**).

CMD

The **CMD** (Command) parameter enables you to specify a full command which will be run against each selected spooled file when WRKSPLFPDM is run in batch mode.

This parameter cannot be used at the same time as the **OPTION** parameter. You may tell WRKSPLFPDM what to do with each spooled file selected *either* by using a standard or user-defined option on the **OPTION** parameter *or* by specifying a full command on the **CMD** parameter, but not both.

The main advantage of using the CMD parameter over the OPTION parameter is that the command you enter will be syntax checked and prompting is available by use of the F4 command. This also allows access to the command help text.

Substitution variables may be used on most parameters (see p88). However, due to constraints imposed by the OS/400 command processor and prompter, substitution variables cannot be entered on the **FROMFILE**, **JOB** and **SPLNBR** parameters. Instead, you should use the special value ***SLT** on those parameters to denote that the command is to be applied to the selected spooled file.

For example:

WRKSPLFPDM

... MODE(*BATCH) CMD('CVTSPLPDF

FROMFILE(*SLT) TOSTMF(''/home/&U/&F.PDF'') JOB(*SLT) SPLNBR(*SLT) STMFOPT(*REPLACE)')

Here, the specified CVTSPLPDF command will be run against each selected spooled file. *SLT is specified for each of the FROMFILE, JOB and SPLNBR parameters to indicate that the spooled file to be processed is the one currently selected by CoolSpools Spool Admin. The stream file created will be named the same as the spooled file (as indicated by &F) and will be placed in the user's home directory (assuming it is named the same as the user profile, which is denoted by &U).

ERRACN

The **ERRACN** (Error action) parameter allows you to control how CoolSpools Spool Admin behaves when the processing of an option against a spooled file ends in error.

Possible values are:

*STOP	(Default) If the processing of an option against a spooled file ends in error, CoolSpools Spool Admin will not process any further options and will immediately report the error.
	In interactive mode, the user will see an error message specific to the failed option in the message subfile followed by message SPL9998 indicating that an error occurred and that option processing was aborted.
	In batch mode, message SPL9998 is issued as an escape message and the job will end abnormally unless this message is monitored by a calling application.
*CONTINUE	If the processing of an option against a spooled file ends in error, CoolSpools Spool Admin will process any further options and will not report the error until all requested options have been attempted.
	In interactive mode, the user will see a message specific to the options attempted in the message subfile followed by message SPL9999 indicating that one or more errors occurred while processing options.
	In batch mode, message SPL9999 is issued as an escape message and the job will end abnormally, but only after all requested options have been attempted.

LOG

The **LOG** (Log options?) parameter allows you to specify whether option processing is logged in the CoolSpools Spool Admin log file.

Possible values are:

*JOBTYPE	(Default) Logging is determined by the job type, interactive or batch. In batch, options will be logged. Interactively, options are not logged.
*YES	Option processing is logged.
*NO	Option processing is not logged.

When logging of option processing is active, CoolSpools Spool Admin writes a record to log file **ST_SPLLOG** every time an option is processed against a spooled file. This information provides a useful audit trail for keeping track of what has happened to a spooled file and can be used to drive applications which manage spooled files. For example, an archiving application could check the log file to ensure that a spooled file has been successfully saved before deleting the spooled file.

JOBD

The **JOBD** (Job description) parameter allows you to specify the job description which is used to submit option processing to batch when F19 is pressed in interactive mode.

Possible values are:

*USRPRF	(Default) The job description associated with the user profile of the user running the WRKSPLFPDM command is used.
jobd_name	Specify the job description to be used.

Working with Spooled Files in Interactive Mode

When WRKSPLFPDM is run in interactive mode, it selects spooled files according to the selection criteria defined on the command parameters and then displays the resulting list on screen for you to work with.

The screen looks something like this. The actual option text will depend on whether the standard options have been customized or not.

CoolSpools Spool Admin V2R1M0 - Work with Spooled files PDM-style

ARIADNE1

Type options, p	press Enter										
1=SNADS send	2=Change		3=Hold		4=Delete			5=Display			
6=Release	7=Messag	es	8=Attributes		S	9=Status		10=PDF			
					Fil	е	User	Fo	rm		
Opt File	Job	User		Number	Nbr		Data	Ту	pe	Sts	5
ST_LICFNCR	SL_BUILD	ARIAD	NE	158805		75		*S	TD	RDY	7
ST_WRKSPLD	ST_BUILD	ARIAD	NE	158808		48		*S	TD	RDY	
ST_USROPTD	ST_BUILD	ARIAD	NE	158808		49		*S	TD	RDY	
ST_STDOPTD	ST_BUILD	ARIAD	NE	158808		50		*S	TD	RDY	
ST_WRKMOND	ST_BUILD	ARIAD	NE	158808		51		*S	TD	RDY	
ST_WRKRULD	ST_BUILD	ARIAD	NE	158808		52		*S	TD	RDY	
ST_WRKSCPD	ST_BUILD	ARIAD	NE	158808		53		*S	TD	RDY	
ST_WRKSCED	ST_BUILD	ARIAD	NE	158808		54		*S	TD	RDY	,
										More.	••
Parameters or o	command										
===>											
F3=Exit	F5=Refresh	F	7=Def	aults	F8	=Se	lect	F11=	View	2	
F12=Cancel	F13=Repeat	F	14=Su	bset	F1	5=S	ort date	F24=	More	keys	-

Pressing F11 displays View 2 showing additional information for the same spooled files.

CoolSpools Spool Admin V2R1M0 - Work with Spooled files PDM-style ARIADNE1

Type options, press Enter.										
1=SNADS send	SNADS send 2=Change		3=Hold	ł	4=Delet	е	5=Display			
6=Release	7=Messages		8=Attributes		9=Statu	S	10=PDF		•••	
	Queue or		C	Creation	Creati	on Nb	or of	Curr	ent	
Opt File	Device	Librar	y I	Date	Time	Pa	ges	Page	E	?ty
ST_LICFNCR	PRT01	QUSRSYS	S 1	7/02/06	00.18.	26	56			5
ST_WRKSPLD	PRT01	QUSRSYS	S 1	7/02/06	00.34.	05	25			5
ST_USROPTD	PRT01	QUSRSYS	S 1	7/02/06	00.34.	07	11			5
ST_STDOPTD	PRT01	QUSRSYS	S 1	7/02/06	00.34.	08	14			5
ST_WRKMOND	PRT01	QUSRSYS	S 1	7/02/06	00.34.	09	12			5
ST_WRKRULD	PRT01	QUSRSYS	S 1	7/02/06	00.34.	10	12			5
ST_WRKSCPD	PRT01	QUSRSYS	S 1	7/02/06	00.34.	11	6			5
ST_WRKSCED	PRT01	QUSRSYS	S 1	7/02/06	00.34.	12	10			5
									Мол	re
Parameters or command										
===>										
F3=Exit	F5=Refresh	F7=	=Defau	ults	F8=Select		F11=V	View	1	
F12=Cancel	F13=Repeat	F14	F14=Subset I		F15=Sort	date	F24=M	lore	keys	

Options

Two types of option can be input against items in the list:

• Standard options.

These include the normal spooled file operations such as 3=Hold, 4=Delete, 6=Release as well as special options requiring other ariadne software such as 10=PDF (Convert to PDF using CoolSpools) and 20=Email PDF (Convert to PDF using CoolSpools and email using CoolSpools Email).

Standard options can be customized using the WRKSTDOPT command.

• User-defined options.

Any entry in the option field which is not recognized as a standard option will be interpreted as a user-defined option.

User-defined options are created with WRKUSROPT.

Whether a given user has authority to run a particular standard or user-defined option is controlled by the user's authority to the appropriate registered function. Refer to the "Authorities" section for further details.

Standard options

The following standard options are shipped with CoolSpools Spool Admin but can be customized using the WRKSTDOPT command.

The underlying command strings are available to view in database file ST_STDOPT.

Standard Options as supplied when CoolSpools Spool Admin first installed

Opt	Text 'Description' Send spooled files	Normal Command String
1	using SNADS	?SNDNETSPLF ?*FILE(&f) ?*JOB(&n/&u/&j) ?*SPLNBR(&s)
2	Change Spooled File	CHGSPLFA FILE(&f) JOB(&n/&u/&j) SPLNBR(&s)
3	Hold spooled file	HLDSPLF FILE(&f) JOB(&n/&u/&j) SPLNBR(&s)
4	Delete spooled file	DLTSPLF FILE(&f) JOB(&n/&u/&j) SPLNBR(&s)
5	Display spooled file	DSPSPLF FILE(&f) JOB(&n/&u/&j) SPLNBR(&s)
6	Release spooled file	RLSSPLF FILE(&f) JOB(&n/&u/&j) SPLNBR(&s)
7	Display spooled file messages Work with spooled file	&C/WRKSPLFMSG MSGQ(&W/&V)
8	attributes Work with printing	WRKSPLFA FILE(&f) JOB(&n/&u/&j) SPLNBR(&s)
9	status Convert spooled file to	&C/WRKPRTSTS FILE(&f) JOB(&n/&u/&j) SPLNBR(&s) &C/CVTSPLPDF FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S)
10	PDF Convert spooled file to	STMFOPT(*REPLACE) &C/CVTSPLXLS FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S)
11	Excel	STMFOPT(*REPLACE)
12	Convert spooled file to HTML	&C/CVTSPLHTML FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT(*REPLACE)
13	Convert spooled file to CSV	&C/CVTSPLCSV FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT(*REPLACE)
14	Convert spooled file to Text	&C/CVTSPLTXT FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT(*REPLACE)
15	Convert spooled file to RTF	&C/CVTSPLRTF FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT(*REPLACE)
16	Convert spooled file to TIFF	&C/CVTSPLTIFF FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT(*REPLACE)
17	Convert spooled file to spooled file	&C/CVTSPLSPLF FROMFILE(&F) TOFILE(&F) JOB(&N/&U/&J) SPLNBR(&S)
20	Émail spooled file as a PDF	&C/CVTSPLPDF FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&Ś.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT('REPLACE) EMAIL('YES)
21	Email spooled file as Excel	&C/CVTSPLXLS FROMFILE(&F) TOŚTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT('REPLACE) EMAIL('YES)
21	Excel Email spooled file as	&C/CVTSPLHTML FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J)
22	HTML Email spooled file as	SPLNBR(&S) STMFOPT(*REPLACE) EMAIL(*YES) &C/CVTSPLCSV FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S)
23	CSV	STMFOPT(*REPLACE) EMAIL(*YES)
24	Email spooled file as Text	&C/CVTSPLTXT FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT(*REPLACE) EMAIL(*YES)
25	Email spooled file as RTF	&C/CVTSPLRTF FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT(*REPLACE) EMAIL(*YES)
26	Email spooled file as TIFF	&C/CVTSPLTIFF FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT(*REPLACE) EMAIL(*YES)
30	Save spooled file	&C/SAVSPLF FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT(*REPLACE)
50	Run script	&C/RUNSPLSCP SPLFNAME(&F) JOB(&N/&U/&J) SPLNBR(&S)
		Vou con clos enter cortain standard entions in the

You can also enter certain standard options in the following form, but be aware that the function performed

CoolSpools Spool Admin User Guide V6R1

Page: 33

by these standard options could differ from that implied by the mnemonic if the option commands have been customized:

*SND=standard option 1 (Send spooled file using SNADS)

*CHG=standard option 2 (Change spooled file attributes)

*HLD=standard option 3 (Hold spooled file)

*DLT=standard option 4 (Delete spooled file)

*DSP=standard option 5 (Display spooled file)

*RLS=standard option 6 (Release spooled file)

*MSG=standard option 7 (Display spooled file messages)

*ATR=standard option 8 (Display spooled file attributes)

*STS=standard option 9 (Display print status)

The text description and the command string that is run when the option is selected can be modified using the WRKSTDOPT command. It is possible to customize standard options at two levels:

- System defaults. Changes made at system default level affect all users who have not customized the own individual standard options
- User. Individual users may customize standard options for their own use.

User-defined options

One of the most powerful features that WRKSPLFPDM has to offer is its ability to process user-defined options and commands that contain substitution variables.

User-defined options can be input against spooled files in the list that is shown when WRKSPLFPDM is run in interactive mode, just as you might enter a PDM user-defined option against an item in a PDM list.

Alternatively, user-defined options can be specified on the OPTION parameter which determines the processing that WRKSPLFPDM or RUNSPLFCMD runs against a set of spooled files when it runs in batch mode.

Finally, user-defined options can be selected as the action to be performed when a spooled file rule is applied to a spooled file.

Function keys

Available function keys are:

F3=Exit	Exit the application.			
F4=Prompt	Prompt a command or option.			
F5=Refresh	Refresh the list.			
F7=Defaults	Change the standard option definitions.			
	Standard option details specified here are saved by user and are separately definable for each user.			

	For a user to be able to change a standard option, the user must be authorized to registered function ARIADNE_STD_OPT_nn_CHG , where nn is the standard option number.
F11=View 1/View 2	Toggles the display between the View 1 and View 2.
F12=Cancel	Return to the previous screen.
F13=Repeat	Repeats an option input against the list to the end of the list (as per PDM).
F14=Subset	Modify the selection criteria to select a different set of spooled files.
F15=Sort by date	Sort the display by date (if not already sorted by date). Displays a date positioner to allow you to position the display by date.
F16=Sort by name	Sort the display by name (if not already sorted by name). Displays a name positioner to allow you to position the display by name.
F17=Top	Position the display to the top of the list.
F18=Bottom	Position the display to the end of the list.
F19=Submit	Submits a job to runs the option in batch.
F20=Prompt/Submit	Prompts the command in the same way as F4, then submits a job to runs the option in batch in the same was as F19.
F23=More options	Displays additional standard options.
F24=More keys	Displays additional function keys

Working with Spooled Files in Batch Mode

The **RUNSPLFCMD** (Run Spooled File Commands) command is identical to WRKSPLFPDM when run in batch mode, i.e. it selects a set of spooled files and runs an option or command against each of those spooled files, but has no user interface. It is basically provided as an alternative to WRKSPLFPDM because some users were uncomfortable with the concept of a "work-with" command which had no user interface!

Parameters are identical to WRKSPLPDM except that the option to run in "interactive" mode is removed.

IMPADMDTA command

You can use the IMPADMDTA (Import Admin Data) command supplied with CoolSpools Spool Admin V6R1M0 to migrate CoolSpools Spool Admin user setup data from CoolTools. This provides a means of preserving data that you have set up such as spooled file rules, monitors and scripts, tailored standard options and user-defined options.

Restrictions

The files in the from- and to-libraries must not be in use at the time when this command is run.

Command parameters are as follows:

FROMLIB

Specifies the library from which the data is to be imported.

Options are:

SPLTLSV2R1	The CoolTools V2R1M0 product library
SPLTLSV1R1	The CoolTools V1R1M0 product library
COOLSPV5R1	The CoolSpools PLUS V5R1M0 product library
name	Specify the name of the library where the data is held.

REPLACE

Specifies whether data in the target files will be replaced if they are not empty. Options are:

*NO	The data is not replaced. The command will fail if the
	target files already contain data.
*YES	Any data in the target files will be overwritten.

WRKSTDOPT (Work with Standard Options)

The **WRKSTDOPT** (Work with Standard Options) command lets you customize the standard options used by the WRKSPLFPDM and RUNSPLFCMD commands, and which can be also be used as actions triggered by spooled file rules.

This command is intended to be an administrator function and is shipped with public *EXCLUDE authority. You will need to be signed on as a user with *ALLOBJ authority, or be granted authority by your security officer, in order to run this option.

The following authority considerations apply (see "Authorities" earlier in this User Guide):

- In order to run WRKSTDOPT to customize the system default standard options, you must have authority to function ARIADNE_STD_OPT_SYS_DFT_CHG
- In order to run WRKSTDOPT to customize the standard options for a user other than yourself, you must have authority to function ARIADNE_STD_OPT_OTH_USR_CHG
- In order to customize a particular option, you must have authority to registered function ARIADNE_STD_OPT_nn_CHG where nn is the option number (two digits 01-12)

The program displays the twelve possible standard options.

ARIADNE1	CoolSpools Spool Admin V2R1M0 - Work with Standard Options
Options for	*SYSDFT System defaults
Type options	s, press Enter.
2=Change	5=Display
Opt Option	Text
01	Send spooled files using SNADS
02	Change Spooled File
03	Hold spooled file
04	Delete spooled file
05	Display spooled file
06	Release spooled file
07	Display spooled file messages
08	Work with spooled file attributes
09	Work with printing status
10	Email spooled file using CoolSpools
11	Convert spooled file using CoolSpools
12	Save spooled file using CoolSpools

The "**Options for**" header field indicates at what level you are customizing the standard options:

• User-level (user name shown)

Any customization made at this level will only affect the running of the standard option in question for the user concerned.

• System defaults (*SYSDFT)

Any customization made at this level will apply system-wide and will affect the running of the standard option in question for all users who do not have a personal customized version of that standard option.

For example, standard option 10 is supplied with the command string set to:

CVTSPLPDF FROMFILE(&F) TOSTMF('&F_&N_&U_&J_&S.&X') JOB(&N/&U/&J) SPLNBR(&S) STMFOPT(*REPLACE)

You may well decide that, for safety's sake, you would like the default value of the STMFOPT parameter to be *NONE rather than *REPLACE. You could change the defined command string for option 10 in WRKSTDOPT at *SYSDFT level and the new value would then be used by all users thereafter,

However, if an individual user decided that he or she would prefer, for the sake of convenience, to have STMFOPT default to *REPLACE, and that user had authority to modify the standard option in question., he/she could modify the command string just for his or her personal usage by running WRKSTDOPT *CURRENT.

Options

Options that can be input against entries in the list are:

2=Change	Change the standard option. The changes you make will affect:	
	 Only the specified user in question if the USER parameter of the WRKSTDOPT command specified a user profile (was not *SYSDFT) 	
	 All users who do not have customized options of their own if the WRKSTDOPT(*SYSDFT) was specified. 	
5=Display	Display the standard option.	
Function keys		
Available function keys are:		
F3=Exit	Exit the application.	

F5=Refresh	Refresh the list.
F10=Normal command	Display the command string used when the standard option is run without prompting (F4).
F11=Prompted command	When the list is showing the command string associated with the user-defined option, pressing F11 displays the descriptive text instead.
F12=Cancel	Return to the previous screen.

Attributes

When a standard option is being created or changed, a screen similar to this one is displayed:

F3=Exit F4=Prompt F12=Cancel F14=Default PgDn=Prompted command

The following attributes are definable:

Text 'description'	A piece of text associated with the user-defined option and intended to describe its purpose or function.
Heading text	A short description of the option which will appear in the option lines at the top of the WRKSPLFPDM screen.
Confirmation required	Whether you will be prompted for confirmation before the option is run (as is normal with option 4=Delete).

Normal command	The command string the system is to run when the option is applied to a spooled file. The string can contain substitution variables (see p88).	
	When defining the command string, F4 can be pressed to prompt the command.	
	The command defined here is the "normal" command which is run when the option is entered and F4 is not pressed to prompt it.	
Prompted command	The command string the system is to run when the option is entered against a spooled file and F4 is pressed to prompt it.	
	The string can contain substitution variables (see p888).	
	The command string must start with the prompt character "?". If a ? is not supplied, CoolSpools Spool Admin will add it for you. You may also specify selective prompting characters before any parameters which you wish to protect from input, hide, supply defaults for etc.	
	See the <u>CL Programming Guide</u> for details of the selective prompt characters that can be used.	

Function keys

Available function keys are:

F3=Exit	Exit the application.
F4=Prompt	Prompt the command string.
F12=Cancel	Return to the previous screen.
F14=Default	If defining a user-level customized command, F14 replaces the command string with the current system default command.
	If defining a system default command, F14 replaces the command string with the system-supplied command string.
F15=Copy normal	When displaying the prompted command string, F15 copies the normal command string to the prompted command string and adds the necessary ? at the beginning.
PgUp=Normal	When displaying the prompted command, Page Up switches to displaying the "normal" command.
PgDn=Prompted Command	When displaying the "normal" command, Page Down switches to displaying the prompted command.

WRKUSROPT (Work with User Options)

The **WRKUSROPT** (Work with User Options) command lets you define user-defined options which can be used in conjunction with the WRKSPLFPDM and RUNSPLFCMD commands, and which can be also be used as actions triggered by spooled file rules.

The program displays a list of existing user-defined options.

CoolSpools Spool Admin V2R1MO - Work with User-defined Options ARIADNE1 Position to Type options, press Enter. 2=Change 3=Copy 4=Delete 5=Display Opt Option Text CR Create spooled file transaction CS CoolSpools

F3=Exit F5=Refresh F6=Add F11=Display command F12=Cancel

Options

Options that can be input against entries in the list are:

2=Change	Change the user-defined option
3=Сору	Copy the selected user-defined option to create a new user-defined option.

CoolSpools Spool Admin User Guide V6R1 www.ariadnesoftware.co.uk Page: 43

4=Delete	Delete the user-defined option.		
5=Display	Display the user-defined option.		
Function keys			
Available function keys are:			
F3=Exit	Exit the application.		
F5=Refresh	Refresh the list.		
F6=Create	Create a new user-defined option.		
F11=Display command	When the list is showing the descriptive text associated with the user-defined option, pressing F11 displays the command string instead.		
F11=Display text	When the list is showing the command string associated with the user-defined option, pressing F11 displays the descriptive text instead.		
F12=Cancel	Return to the previous screen.		

Attributes

When a user-defined option is being created or changed, a screen similar to this one is displayed:

Create User-Defined Option Type choices, press Enter. Option Text 'description' . . . *BLANK Command string

F3=Exit F4=Prompt F12=Cancel

The following attributes are definable:

Text 'description'	A piece of text associated with the user-defined option and intended to describe its purpose or function.
Command string	The command string the system is to run when the option is applied to a spooled file. The string can contain substitution variables (see p888).

When defining the command string, F4 can be pressed to prompt the command.

<u>Setting up CoolSpools Spool Admin to process spooled files</u> <u>automatically</u>

Using the Wizard

The simplest and easiest way to set up CoolSpools Spool Admin to process spooled files automatically is to use the **Automatic spooled file processing setup wizard**.

The wizard can be accessed in several ways:

- 1. By taking option 20 from the CoolSpools Spool Admin Menu
- 2. By running command CFGSPLMON (Configure Spooled File Monitoring)
- 3. By using WRKSPLFPDM to locate a sample spooled file of the type you want to set up automatic processing for, and taking option 34 against it.

The Wizard simplifies the setting up of automatic processing of spooled files by guiding you through the steps required and prompting for selection of output queues to watch, spooled files to select and actions to perform.

Manual Setup

Alternatively, you can follow these steps.

Create spooled file monitors

Using the WRKSPLMON or CRTSPLMON commands, or CoolSpools Spool Admin menu option 21, define one or more spooled file monitors. Each spooled file monitor will detect new spooled files being created with a status of "ready" on one or more output queues by associating a data queue with those output queues and waiting for messages to arrive on the data queue.

It is possible to specify up to 20 output queues to be monitored by a single spooled file monitor (more than 20 is be possible if a generic output queue name or *ANY is specified).

However, it should be borne in mind that using a single spooled file monitor to detect messages generated for multiple output queues could mean that the spooled file monitor job might become a bottleneck if the volume of spooled files being created is large, since all spooled file messages will be processed by a single monitor job. Better throughput may be achieved by defining a separate monitor for each output queue, unless the number of output queues to be monitored is large, in which case the number of monitor jobs might become excessive. A balance must be struck between having too many messages being processed by each monitor job and having too many monitor jobs.

Create spooled file scripts

It is likely that, for every spooled file that you wish to process, you will want a set of actions to be carried out against that spooled file. The simplest way in which to define a set of actions of this kind is to create a spooled file script.

Use the WRKSPLSCP or CRTSPLSCP commands, or option 22 from the CoolSpools Spool Admin menu, to define spooled file scripts and their entries.

If you are going to use spooled file scripts, they must be created prior to trying to refer to them in a spooled file rule.

Create spooled file rules

You must now define the rules which tell CoolSpools Spool Admin what to do for each spooled file that is created. Use the WRKSPLRUL or CRTSPLRUL commands, or select option 23 from the CoolSpools Spool Admin menu, to define spooled file rules.

If you wish to specify rules that work on an exception basis, this is possible by using the "rule priority" and "no error action" attributes together with OPTION(*NONE).

For example, assume you do not wish to process any spooled files created by a system user profile (identified as a user profile starting with a Q, e.g. QSECOFR, QSYSOPR, QPGMR etc.). By assigning a high rule priority, you ensure that this rule is processed before any more specific rules. By specifying NOERRACN(*STOP), you indicate that once the rule has been selected, no other rules should be processed against the spooled file. And by entering OPTION(*NONE), you tell CoolSpools Spool Admin not to take any action against the spooled file.

So, the following command defines a rule which would exclude from processing all spooled files created by users whose name starts with a Q:

CRTSPLRUL USER(Q*) RULEPY(1) OPTION(*NONE) NOERRACN(*STOP)

Start Spooled File Monitoring

Once you have defined your monitor, scripts and rules, you must start the CoolSpools Spool Admin jobs before spooled file processing will take place. Use the STRMONSPLF command or select option 31 from the CoolSpools Spool Admin menu to start the CoolSpools Spool Admin jobs.

Checking Spooled File Processing

In order to check the progress of CoolSpools Spool Admin processing, to ensure that backlogs and bottlenecks are not developing, and to resolve any errors that may have occurred, you should use the WRKTRNSTS and WRKSPLTRN commands, or select options 41-44 from the CoolSpools Spool Admin menu periodically.

Resolving errors

If an error occurs during the processing of a transaction, and that error is not ignored (because it was included in the list of errors to be ignored on the IGNMSGID parameter of the CRTSPLRUL, ADDSPLSCPE commands etc.), CoolSpools Spool Admin will flag the transaction, and the transaction rule step in relation to which the error occurred, as being "in error".

Transactions that are flagged as being "in error" will not be retried until you tell CoolSpools Spool Admin to do so by selecting option 1 against them in the WRKSPLTRN display list. This will remove the error flag and make the transaction available for processing again.

Processing of the transaction will restart from the first transaction rule step which was not successfully processed already

WRKSPLMON (Work with Spooled File Monitors)

The **WRKSPLMON** (Work with Spooled File Monitors) command lets you define spooled file monitors.

A spooled file monitor is a job which monitors for the arrival of spooled files in a ready status on one or more specified output queues. The spooled file monitor is thus the mechanism whereby CoolSpools Spool Admin detects spooled files that it needs to process.

See Page 16 for a further discussion of what a spooled file monitor is and what it does.

The program displays a list of the various monitors which are already defined.

Note that changes to spooled file monitors do not take effect until CoolSpools Spool Admin jobs are restarted.

 ARIADNE1

 Position to

 Type options, press Enter.

 2=Change
 3=Copy
 4=Delete

 Opt Monitor
 Text

 DUMPS
 Monitor for QEZDEBUG

 JOBLOGS
 Monitor for QEZJOBLOG

 QPRINT
 Monitor for QPRINT

F3=Exit	F5=Refresh	F6=Add	F11=Display outqs	F12=Cancel

Options

Options that can be input against entries in the list are:

CoolSpools Spool Admin User Guide V6R1

www.ariadnesoftware.co.uk

Bottom

2=Change	Change the spooled file monitor. Prompts the CHGSPLMON command.
3=Сору	Copy the selected spooled file monitor to create a new spooled file monitor. Prompts the CPYSPLMON command.
4=Delete	Delete the spooled file monitor.

Function keys

Available function keys are:

F3=Exit	Exit the application.
F5=Refresh	Refresh the list.
F6=Create	Create a new spooled file monitor. Prompts the CRTSPLMON command.
F11=Display outqs	When the list is showing the descriptive text associated with the user-defined option, pressing F11 displays the output queues processed by the spooled file monitor.
F11=Display text	When the list is showing the output queues associated with the spooled file monitor, pressing F11 displays the descriptive text instead.
F12=Cancel	Return to the previous screen.

Attributes

When a spooled file monitor is being created or changed, the following attributes are definable:

Spooled file monitor name Output queue	The name by which the monitor will be identified. Specify one or more output queues which this spooled file monitor will govern. The monitor job will use the data queue specified below to detect spooled files being created on the specified output queue(s) with a status of "Ready".
	If you specify a generic name (e.g. QPRINT*) or *ANY for either the output queue name or output queue library, any entries that appear on the data queue which match these names will be selected for processing.
Data queue	Specify the name of the data queue to be used to detect spooled files being created on the output queues listed above.

	The default is *OUTQ, which indicates that the data queue already associated with the output queue(s) defined above will be used. This value is not permitted if the list of output queue names includes *ANY or a generic name.
	The special value *OUTQNAME indicates that CoolSpools should use a data queue of the same name as the output queue specified. This value is not permitted if more than one output queue is specified or if the output queue name is *ANY or a generic name.
	The special value *OUTQLIB for the data queue library indicates that CoolSpools should use a data queue in the same library as the output queue specified. This value is not permitted if more than one output queue is specified or if the output queue name is *ANY or a generic name.
Change outq, if required	Whether CoolSpools Spool Admin is permitted to change the attributes of the output queue(s) specified if this is necessary. CoolSpools Spool Admin will need to modify the output queue(s) if the data queue specified is not already associated with the output queue(s).
Create data queue, if required	Whether CoolSpools Spool Admin is permitted to create the data queue if it does not already exist.
Data queue attributes	The attributes to be used when creating the data queue, if it does not already exist. Display the help text associated with the CRTDTAQ command for details.
Text 'description'	The descriptive text to be associated with the spooled file monitor.

Other commands for working with spooled file monitors

As well as using the **WRKSPLMON** command to work with spooled file monitors, you can manage spooled file monitors from the command line or from a program using the following commands:

CRTSPLMON (Create Spooled File Monitor)

Creates a new spooled file monitor.

CHGSPLMON (Change Spooled File Monitor)

Changes a spooled file monitor,

CPYSPLMON (Copy Spooled File Monitor)

Copies a monitor to create a new monitor.

DLTSPLMON (Delete Spooled File Monitor)

Deletes a monitor.

WRKSPLSCP (Work with Spooled File Scripts)

The **WRKSPLSCP** (Work with Spooled File Scripts) command lets you define spooled file scripts.

A **spooled file script** provides a way of specifying a group of actions which will occur together in specified sequence. Each individual action is defined as a **spooled file script entry** which can be:

- a standard spooled file option
- a user-defined option
- a command string
- a call to another script.

Each spooled file script consists of between zero or more script entries (maximum 9,999).

The program displays a list of the various scripts which are already defined.

Note that changes to scripts take effect immediately if CoolSpools Spool Admin jobs are active.

ARIADNE1	CoolSpools Spool	Admin V2R1M0 -	Work with Spooled	File Scripts
Position to				
Type options,	press Enter.			
2=Change	З=Сору	4=Delete	8=Work with s	script entries
Opt Script	Text			
DUMPS	Process dumps			
JOBLOGS	Process joblogs	3		

Bottom

Options

Options that can be input against entries in the list are:

2=Change	Change the spooled file script. Prompts the CHGSPLSCP command.
3=Сору	Copy the selected spooled file script to create a new spooled file script. Prompts the CPYSPLSCP command.
4=Delete	Delete the spooled file script.
8=Work with script entries	Work with the script entries for the specified script Prompts the WRKSPLSCPE command.

Function keys

Available function keys are:

F3=Exit	Exit the application.
F5=Refresh	Refresh the list.
F6=Create	Create a new spooled file script. Prompts the CRTSPLSCP command.
F12=Cancel	Return to the previous screen.

Attributes

When a spooled file script is being created or changed, the following attributes are definable:

Spooled file script name	The name by which the script will be identified.
Text 'description'	The descriptive text to be associated with the spooled file script.

Other commands for working with scripts

As well as using the **WRKSPLSCP** command to work with scripts, you can manage scripts from the command line or from a program using the following commands:

CRTSPLSCP (Create Spooled File Script)

Creates a new spooled file script.

CHGSPLSCP (Change Spooled File Script)

Changes a spooled file script,

CoolSpools Spool Admin User Guide V6R1

CPYSPLSCP (Copy Spooled File Script)

Copies a script to create a new script.

DLTSPLSCP (Delete Spooled File Script)

Deletes a script.

RUNSPLSCP (Run Spooled File Script)

Runs a script against a specified spooled file. If no script name is supplied, you will be prompted to select one.

The OVRPARM parameter can be used to override command parameters associated with script entries.

WRKSPLSCPE (Work with Spooled File Script Entries)

The **WRKSPLSCPE** (Work with Spooled File Script Entries) command lets you define spooled file script entries.

A **spooled file script** provides a way of specifying a group of actions which will occur together in specified sequence. Each individual action is defined as a **spooled file script entry** which can be:

- a standard spooled file option
- a user-defined option
- a command string
- a call to another script.

Each spooled file script consists of between zero or more script entries (maximum 9,999).

You can run this command by taking option 8 against a script in the WRKSPLSCP (Work with Spooled File Scripts) display or by running the WRKSPLSCPE command itself from the command line. It you run WRKSPLSCPE itself from the command line, you must specify the name of the script whose entries you wish to work with on the **SCRIPT** parameter.

The program displays a list of the script entries which are already defined for the specified script.

Note that changes to scripts take effect immediately if CoolSpools Spool Admin jobs are active.

```
CoolSpools Spool Admin V2R1M0 - Work with Splf Script Entries
ARIADNE1
Script name . : JOBLOGS Process joblogs
Position to . .
Type options, press Enter.
  2=Change
                   3=Copy
                           4=Remove
Opt
              Text
       Seq
       100
              Hold the spooled file
       400
              Delete the spooled file
                                                                        Bottom
F3=Exit
          F5=Refresh
                                   F11=Display text
                                                      F12=Cancel
                         F6=Add
CoolSpools Spool Admin User Guide V6R1
                                                               Page: 56
```

www.ariadnesoftware.co.uk

Options

Options that can be input against entries in the list are:

2=Change	Change the spooled file script entry. Prompts the CHGSPLSCPE command.
3=Сору	Copy the selected spooled file script entry to create a new spooled file script entry. Prompts the CPYSPLSCPE command.
4=Remove	Remove the spooled file script entry.

Function keys

Available function keys are:	
F3=Exit	Exit the application.
F5=Refresh	Refresh the list.
F6=Add	Add a new spooled file script entry. Prompts the ADDSPLSCPE command.
F11=Display script entry	When the script entry text description is displayed in the list, pressing F11 displays brief details of the action associated with the script entry instead.
F11=Display text	When brief details of the action associated with the script entry is displayed in the list, pressing F11 displays the script entry text description instead.
F12=Cancel	Return to the previous screen.

Parameters

When a spooled file script entry is being added or changed, the following parameters are definable:

SCRIPT	Spooled file script name.
	The name of the script to which the entry relates.
SEQNBR	Sequence number.
	A number which identifies the entry within the script and determines the order in which script entries are processed.
OPTION	Option.

	The action to be carried out when the script entry is executed.
	This can either be a CoolSpools Spool Admin standard option, a CoolSpools Spool Admin user- defined option, a command or a call to another script.
	Alternatively, you can enter either a user-defined option (defined using WRKUSROPT).
	In addition, the following two special options are also available:
	*CMD . This indicates that you will define an ad hoc command to be run on the CMD parameter.
	*SCRIPT. This indicates that you will specify a script to be called on the SCRIPT parameter.
OPTPARM	Option parameters.
	Additional parameters associated with the standard or user-defined option specified on the OPTION parameter.
	For example, if you specify OPTION(*CHG) to indicate that CoolSpools Spool Admin should change the spooled file attributes, you can specify the actual attributes to be change on the OPTPARM parameter, e.g.:
	OPTION(*CHG) OPTPARM('OUTQ(QPRINT)')
	The parameter string may include substitution variables (see p888).
CMD	Command to run.
	The command string to be executed. This parameter is only available when OPTION(*CMD) is specified.
	The command string may include substitution variables where the OS/400 command prompter will accept them (see p888).
SCRIPT	Script name.
	The name of another script to be run. A script may not run itself.
TEXT	Text 'description'.
	The descriptive text to be associated with the spooled file script.
NOERRACN	No error action.
	The action to be taken when the action is executed without an error (i.e. no escape message is issued).
CoolSpools Spool Admin User Guide V6R1	Page: 58

www.ariadnesoftware.co.uk

	* CONTINUE (default). Processing continues with the next script entry.
	*STOP . No further processing of script entries occurs.
ERRACN	Error action.
	The action to be taken when the action is executed and an error occurs (i.e. an escape message is issued).
	*STOP (default) No further processing of script entries occurs.
	*CONTINUE . Processing continues with the next script entry. The error is ignored.
IGNMSGID	Ignore message ids
	A list of up to 100 message identifiers. If an error is reported and the error message identifier is in this list, the error will be ignored and processing will continue as if no error had occurred.
	For example, if you wish to hold spooled files, you can specify:
	OPTION(*HLD) IGNMSGID(CPF3337)
	and if the spooled file is already held, the error message CPF3337, which results when you try to hold a spooled file which is already held, will be ignored.

Note that since the sequence number acts as the identifier for a script entry within a script as well as determining the sequence in which entries are processed, it is not possible to change the sequence number of a script entry once it has been created. Instead, if you wish to change the sequence number of a script entry, you should copy the existing script entry to a new script entry with the required sequence number, then remove the original script entry.

Other commands for working with script entries

As well as using the **WRKSPLSCPE** command to work with script entries, you can manage script entries from the command line or from a program using the following commands:

ADDSPLSCPE (Add Spooled File Script Entry)

Adds a script entry to a script.

CHGSPLSCPE (Change Spooled File Script Entry)

Changes a script entry,

CPYSPLSCPE (Copy Spooled File Script Entry)

Copies a script entry to create a new script entry.

CoolSpools Spool Admin User Guide V6R1

RMVSPLSCPE (Remove Spooled File Script Entry)

Removes a script entry from a script.

WRKSPLRUL (Work with Spooled File Rules)

The **WRKSPLRUL** (Work with Spooled File Rules) command lets you define spooled file rules.

Once a spooled file monitor job has detected that a spooled file has been created, CoolSpools Spool Admin needs to know what to do with it. You tell it what to do with different types of spooled files by defining **spooled file rules**.

A spooled file rule basically consists of:

- A set of **criteria** which are compared with the spooled file's attributes and determine whether the rule is selected or not
- An **action** to be performed against the spooled file when the spooled file matches the criteria and is selected to be processed

The program displays a list of the rules which have already been defined.

Note that changes to rules can take effect immediately (if ACTIVATE(*IMMED) is specified) and CoolSpools Spool Admin jobs are active, or only when the CoolSpools Spool Admin jobs are restarted (if ACTIVATE (*DLY) is specified or the CoolSpools Spool Admin jobs are not active).

 CoolSpools Spool Admin V2R1M0 - Work with Spooled File Rules

 ARIADNE1

 Position to

 Type options, press Enter.

 2=Change
 3=Copy

 4=Delete

 Opt Rule
 Text

 JOBLOGS
 Rule for joblogs

 PGM_DUMPS
 Rule for program dumps

 SVC_DUMPS
 Rule for service dumps

Bottom

F3=Exit F5=Refresh F6=Add F11=Display criteria F12=Cancel

CoolSpools Spool Admin User Guide V6R1

Page: 61

Options

Options that can be input against entries in the list are:

2=Change	Change the spooled file rule. Prompts the CHGSPLRUL command.
3=Сору	Copy the selected spooled file rule to create a new spooled file rule. Prompts the CPYSPLRUL command.
4=Delete	Delete the spooled file rule.

Function keys

Available function keys are:	
F3=Exit	Exit the application.
F5=Refresh	Refresh the list.
F6=Create	Create a new spooled file rule. Prompts the CRTSPLRUL command.
F11=Display criteria	When the rule text description is displayed in the list, pressing F11 displays brief details of the criteria associated with the rule instead.
F11=Display text	When brief details of the criteria associated with the rule are displayed in the list, pressing F11 displays the rule text description instead.
F12=Cancel	Return to the previous screen.

Parameters

When a spooled file rule is being created, copied or changed, the following parameters are definable:

RULE	Spooled file rule name.
	The name by which the rule will be identified.
USER	User.
	Enter the name of the user who created the spooled files to be selected by this rule.
	A generic name may be entered (e.g. Q*)
	*ALL (default) = All users
SPLFNAME	Spooled file name.

	Enter the name of the spooled file to be selected by this rule.
	A generic name may be entered (e.g. QSYS*)
	*ALL (default) = All spooled files.
PRTDEV	Print device.
	Enter the name of the printer device with which spooled files must be associated to be selected by this rule.
	A generic name may be entered (e.g. QSYS*)
	*ALL (default) = All printer devices.
OUTQ	Output queue.
	Enter the name of the output queue with which spooled files must be associated to be selected by this rule.
	A generic name may be entered (e.g. QPRINT*)
	*ALL (default) = All output queues.
	*ANY = Any output queue in the specified library.
FORMTYPE	Form type.
	Enter the form type which the spooled file must have to be selected by this rule.
	A generic value may be entered (e.g. INVOICE*)
	*ALL (default) = All form types
	*STD = The standard form type.
USRDTA	User data.
	Enter the user data value which the spooled file must have to be selected by this rule.
	A generic value may be entered (e.g. SALES*)
	*ALL (default) = All user data values.
JOB	Job name.
	Enter the name of the job which must have created the spooled file in order for it to be selected by this rule.
	A generic name may be entered (e.g. QPADEV*)
	*ALL (default) = All jobs
PGM	Created by program.
	Enter the name of the program which must have created the spooled file in order for it to be selected by this rule.
	A generic name may be entered (e.g. Q*)
CoolSpools Spool Admin User Cuide V6D1	Page: 63
CoolSpools Spool Admin User Guide V6R1	rage: 03

www.ariadnesoftware.co.uk

	*ALL (default) = All programs
	* ANY = Any program in the specified library
DEVTYPE	Printer device type
	Enter the printer device type attributes which the spooled file must have in order for it to be selected by this rule.
	*ALL (default) = All types
	*SCS = SCS (SNA Character String)
	*IPDS = IPDS (Intelligent Printer Data Stream)
	* AFPDS = AFP (Advanced Function Printing Data Stream).
	*AFPDSLINE = Mixed AFP and line data
	*LINE = Line data
	*USERASCII = ASCII data stream
NBRPAGES	Number of pages.
	Enter the range in which the spooled file's number of pages attribute must fall in order for this rule to be selected.
	*ALL (default) = Any number of pages
	— 1 <i>(((((((((((((</i>
	The upper value of the range can be specified as *MAX = no upper limit.
SPLFSIZE	
SPLFSIZE	*MAX = no upper limit.
SPLFSIZE	 *MAX = no upper limit. Spooled file size (Kb) Enter the range in which the spooled file's data size attribute must fall in order for this rule to be
SPLFSIZE	*MAX = no upper limit. Spooled file size (Kb) Enter the range in which the spooled file's data size attribute must fall in order for this rule to be selected.
SPLFSIZE	 *MAX = no upper limit. Spooled file size (Kb) Enter the range in which the spooled file's data size attribute must fall in order for this rule to be selected. The value is measured in kilobytes (1024 bytes).
SPLFSIZE	 *MAX = no upper limit. Spooled file size (Kb) Enter the range in which the spooled file's data size attribute must fall in order for this rule to be selected. The value is measured in kilobytes (1024 bytes). *ALL (default) = Any size The upper value of the range can be specified as
	 *MAX = no upper limit. Spooled file size (Kb) Enter the range in which the spooled file's data size attribute must fall in order for this rule to be selected. The value is measured in kilobytes (1024 bytes). *ALL (default) = Any size The upper value of the range can be specified as *MAX = no upper limit.
	 *MAX = no upper limit. Spooled file size (Kb) Enter the range in which the spooled file's data size attribute must fall in order for this rule to be selected. The value is measured in kilobytes (1024 bytes). *ALL (default) = Any size The upper value of the range can be specified as *MAX = no upper limit. Rule priority A value between 1 and 9999 controlling the order in which rules will be processed when more than one is selected. The lower the priority, the earlier
	 *MAX = no upper limit. Spooled file size (Kb) Enter the range in which the spooled file's data size attribute must fall in order for this rule to be selected. The value is measured in kilobytes (1024 bytes). *ALL (default) = Any size The upper value of the range can be specified as *MAX = no upper limit. Rule priority A value between 1 and 9999 controlling the order in which rules will be processed when more than one is selected. The lower the priority, the earlier the rule will be processed.
RULEPTY	 *MAX = no upper limit. Spooled file size (Kb) Enter the range in which the spooled file's data size attribute must fall in order for this rule to be selected. The value is measured in kilobytes (1024 bytes). *ALL (default) = Any size The upper value of the range can be specified as *MAX = no upper limit. Rule priority A value between 1 and 9999 controlling the order in which rules will be processed when more than one is selected. The lower the priority, the earlier the rule will be processed. Default = 5000.

	This can either be a CoolSpools Spool Admin standard option, a CoolSpools Spool Admin user- defined option, a command or a call to another script.
	Alternatively, you can enter a CoolSpools Spool Admin user-defined option (defined using WRKUSROPT).
	In addition, the following two special options are also available:
	*CMD . This indicates that you will define an ad hoc command to be run on the CMD parameter.
	*SCRIPT. This indicates that you will specify a script to be called on the SCRIPT parameter.
OPTPARM	Option parameters.
	Additional parameters associated with the standard or user-defined option specified on the OPTION parameter.
	For example, if you specify OPTION(*CHG) to indicate that CoolSpools Spool Admin should change the spooled file attributes, you can specify the actual attributes to be change on the OPTPARM parameter, e.g.:
	OPTION(*CHG) OPTPARM('OUTQ(QPRINT)')
	The parameter string may include substitution variables (see p888).
CMD	Command to run.
	The command string to be executed. This parameter is only available when OPTION(*CMD) is specified.
	The command string may include substitution variables where the OS/400 command prompter will accept them (see p888).
SCRIPT	Script name.
	The name of a spooled file script to be run.
ТЕХТ	Text 'description'.
	The descriptive text to be associated with the spooled file script.
NOERRACN	No error action.
	The action to be taken when the option, script or command is executed without an error (i.e. no escape message is issued).
	*CONTINUE (default). Processing continues with the next rule.
olSpools Spool Admin User Guide V6R1	Page: 65

CoolSpools Spool Admin User Guide V6R1

	*STOP . No further processing of rules occurs.
ERRACN	Error action.
	The action to be taken when the option, script or command is executed and an error occurs (i.e. an escape message is issued).
	*STOP (default) No further processing of rules occurs.
	* CONTINUE . Processing continues with the next rule. The error is ignored.
ACTIVATE	When to activate changes
	Whether the changes should be activated immediately or only when CoolSpools Spool Admin jobs are restarted.
	*IMMED (default). The changes take effect immediately. If CoolSpools Spool Admin jobs are currently active, the processing of spooled files will begin to use the new rules from now onwards.
	*DLY. The changes will not take effect immediately. If CoolSpools Spool Admin jobs are currently active, the processing of spooled files will continue using the rules that existed when the jobs started or when the last set of rule changes was activated.
IGNMSGID	Ignore message ids
	A list of up to 100 message identifiers. If an error is reported and the error message identifier is in this list, the error will be ignored and processing will continue as if no error had occurred.
	For example, if you wish to hold spooled files, you can specify:

OPTION(*HLD) IGNMSGID(CPF3337)

and if the spooled file is already held, the error message CPF3337, which results when you try to hold a spooled file which is already held, will be ignored.

Other commands for working with rules

As well as using the **WRKSPLRUL** command to work with rules, you can manage rules from the command line or from a program using the following commands:

CRTSPLRUL (Create Spooled File Rule)

Creates a spooled file rule

CoolSpools Spool Admin User Guide V6R1

CHGSPLRUL (Change Spooled File Rule)

Changes a spooled file rule

CPYSPLRUL (Copy Spooled File Rule)

Copies a spooled file rule to create a new spooled file rule.

DLTSPLRUL (Delete Spooled File Rule)

Deletes a spooled file rule.

CoolSpools Spool Admin Jobs

Work Management

In order to detect and process spooled files, CoolSpools Spool Admin needs a number of jobs to be started.

All of these jobs use a job description called **COOLSPOOLS SPOOL ADMIN**. When first installed, this job description is configured to use a job queue called **COOLSPOOLS SPOOL ADMIN**, which feeds into a subsystem called **COOLSPOOLS SPOOL ADMIN**.

If you wish to run these jobs in a different subsystem, you will need to modify the **COOLSPOOLS SPOOL ADMIN** job description to use a different job queue, or add a job queue entry for the **COOLSPOOLS SPOOL ADMIN** job queue to a different subsystem.

Job description **COOLSPOOLS SPOOL ADMIN** is also configured so that jobs run under user profile QSYSOPR. If this is inappropriate to your environment, you can change the job description so that they use a different user profile. However, you must ensure that the user profile you select has all the necessary authorities. This should include spool and job control special authorities.

It is important to realize that no spooled file processing will occur unless these CoolSpools Spool Admin jobs are active. You should therefore consider including the startup of these jobs in your system startup procedures. There are two possible approaches to this:

a) Include the STRMONSPLF command in your system startup program and specify STRSBS(*YES) RLSJOBQ(*YES) to ensure that the COOLSPOOLS SPOOL ADMIN subsystem has been started and the COOLSPOOLS SPOOL ADMIN job queue released.

Note that if you are running the CoolSpools Spool Admin jobs in a different subsystem or submitting them to a different job queue, you will need to ensure that this subsystem is active and the job queue released manually, as CoolSpools Spool Admin will no longer be responsible for controlling that aspect of the system.

b) A job description called ST_STARTUP is supplied with CoolSpools Spool Admin. This is intended for use with an auto-start job. If you add an auto-start job to the COOLSPOOLS SPOOL ADMIN subsystem description or another subsystem description, specify this job description and the CoolSpools Spool Admin jobs will start automatically when the subsystem is started.

For example:

ADDAJE SBSD(COOLSPOOLS SPOOL ADMIN) JOB(ST_STARTUP) JOBD(ST_STARTUP)

You then need to ensure that the subsystem is started as part of your system startup procedures.

Jobs

There are three types of job which CoolSpools Spool Admin runs and needs to be active in order to process spooled files successfully,

Control

A single CoolSpools Spool Admin Control Job submits communicates with and manages all of

CoolSpools Spool Admin User Guide V6R1

	the other CoolSpools Spool Admin jobs. It is submitted when you run STRMONSPLF.
	Its name is ST_CTLSPLR.
Monitor	One CoolSpools Spool Admin Monitor Job will be started for each spooled file monitor that has been defined.
	The purpose of these jobs is to monitor for spooled file messages on the associated data queue and create spooled file transactions to be processed.
	The monitor jobs have the same name as the spooled file monitor definition the job is implementing. For example, if you create a spooled file monitor called JOBLOGS , the job which monitors for spooled files using this definition will be called JOBLOGS too.
Processor	One or more CoolSpools Spool Admin Processor Jobs will be started by the CoolSpools Spool Admin Control Job.
	The number of processor jobs that is started initially is determined by the value of the NBRPRCJOBS parameter of the STRMONSPLF command which started the Control Job.
	Basically, these jobs represent a pool of resources which is available to process spooled file transactions which are waiting to be worked on. The optimum number of processor jobs will depend on the capacity of your machine. The default for NBRPRCJOBS is 4. If you find that spooled file transactions are not being processed quickly enough, and appear to be waiting to be processed, you should try starting a larger number of processor jobs. Eventually there will come a point where the extra load on the system of starting an additional processor job will outweigh the benefit of having that additional job available for work. The point where this will be reached depends on many factors and is most likely to be determined by trial and error.
	You can start additional processor jobs and end processor jobs that are no longer required using the STRPRCJOB and ENDPRCJOB commands. These commands provide a more convenient way of managing the number of available processor jobs than the STRMONSPLF and ENDMONSPLF commands, which start and end all spooled file activity.
	The pressess ishe are called CT DDCCDLD

The processor jobs are called **ST_PRCSPLR**,

STRMONSPLF (Start Monitoring Spooled Files)

The **STRMONSPLF** (Start Monitoring Spooled Files) command starts the CoolSpools Spool Admin jobs which monitor and process spooled files.

Unless these jobs are active, no spooled files will be processed by CoolSpools Spool Admin. See the section on CoolSpools Spool Admin Jobs for a discussion of the different types of jobs and their importance.

Parameters

When a spooled file rule is being created, copied or changed, the following parameters are definable:

NBRPRCJOBS	Number of processing jobs
	The number of processing jobs to start initially.
	See the section on CoolSpools Spool Admin jobs for a discussion of processing jobs and how to determine the optimum number to run simultaneously.
	Additional processing jobs can be started, and unwanted jobs ended, by means of the STRPRCJOB and ENDPRCJOB commands respectively.
STRSBS	Start subsystem
	Whether CoolSpools Spool Admin should start the COOLSPOOLS SPOOL ADMIN subsystem if it is not already active.
	*YES= Yes, start the subsystem.
	*NO = No, do not start the subsystem.
	When first installed, CoolSpools Spool Admin is configured to submit CoolSpools Spool Admin jobs to the COOLSPOOLS SPOOL ADMIN job queue. The CoolSpools Spool Admin job queue is configured to feed into the COOLSPOOLS SPOOL ADMIN subsystem. In order for CoolSpools Spool Admin jobs to run, the job queue must be released and the subsystem must be started.
	If you have modified this configuration, it is your responsibility to ensure that the appropriate job queue has been released and the appropriate subsystem started.
RLSJOBQ	Release job queue
	Whether CoolSpools Spool Admin should release the COOLSPOOLS SPOOL ADMIN job queue if it is held.

*YES= Yes, release the job queue.

*NO = No, do not release the job queue.

When first installed, CoolSpools Spool Admin is configured to submit CoolSpools Spool Admin jobs to the COOLSPOOLS SPOOL ADMIN job queue. The CoolSpools Spool Admin job queue is configured to feed into the COOLSPOOLS SPOOL ADMIN subsystem. In order for CoolSpools Spool Admin jobs to run, the job queue must be released and the subsystem must be started.

If you have modified this configuration, it is your responsibility to ensure that the appropriate job queue has been released and the appropriate subsystem started.

ENDMONSPLF (End Monitoring Spooled Files)

The **ENDMONSPLF** (End Monitoring Spooled Files) command ends the CoolSpools Spool Admin jobs which monitor and process spooled files.

Unless these jobs are active, no spooled files will be processed by CoolSpools Spool Admin. See the section on CoolSpools Spool Admin Job for a discussion of the different types of jobs and their importance.

Once this command has been run, the control and monitor jobs will end almost immediately. Processing jobs which are not currently working on a transaction will also end almost immediately. However, processing jobs which are working on a transaction will attempt to complete the current transaction step before ending. If this step does not complete within 10 minutes, the job will end abnormally. The transaction step will be restarted from the beginning the next time the CoolSpools Spool Admin jobs are started. You should bear this in mind when defining spooled file rules and scripts.

STRPRCJOB (Start Processing Jobs)

The **STRPRCJOB** (Start Processing Jobs) command starts one or more CoolSpools Spool Admin processing jobs.

See the section on CoolSpools Spool Admin Jobs for a discussion of the different types of jobs and their importance.

Parameters

NBRPRCJOBS

Number of processing jobs

The number of processing jobs to start.

See the section on CoolSpools Spool Admin jobs for a discussion of processing jobs and how to determine the optimum number to run simultaneously.

ENDPRCJOB (End Processing Jobs)

The **ENDPRCJOB** (End Processing Jobs) command ends one or more CoolSpools Spool Admin processing jobs.

See the section on CoolSpools Spool Admin Jobs for a discussion of the different types of jobs and their importance.

Parameters

NBRPRCJOBS

Number of processing jobs

The number of processing jobs to end.

See the section on CoolSpools Spool Admin jobs for a discussion of processing jobs and how to determine the optimum number to run simultaneously.

WRKSPLTRN (Work with Spooled File Transactions)

The **WRKSPLTRN** (Work with Spooled File Transactions) command lets you work with spooled file transactions and provides a convenient place to carry out a number of operational tasks related to spooled file processing, such as ensuring that no errors have occurred and resolving any errors that have occurred.

ARIADNE1	CoolSpool	s Spool Adm	in V2R1M0 -	Work with	Spooled Fi	le Transac	tions:
		Unproce	ssed Transa	ctions			
Position to	date/time				Tot	al:	1244
Position to	transactio	n					
							E
Type option	s, press En	ter.					Вr
1=Resubmi	t 4=Dele	te 5=Dis	play 8=E:	rrors			u r
					Creat	ion	s o
Trn Nbr	Status	Splf Name	Job	User	Date	Time	y r
3076	Received	QPJOBLOG	QBATCH	QSYS	12/10/04	20:10:38	} *
3075	Selected	QPJOBLOG	ST_WRKTRNR	ARIADNE	12/10/04	19:03:16	5 *
2964	Selected	QPJOBLOG	P000000271	QSYSOPR	12/10/04	17:18:13	} *
2963	Selected	QPJOBLOG	P000000272	QSYSOPR	12/10/04	17:18:11	. *
2962	Selected	QPJOBLOG	P000000270	QSYSOPR	12/10/04	17:18:06	5 *
2960	Selected	QPJOBLOG	P000000268	QSYSOPR	12/10/04	17:18:02	2 *
2959	Selected	QPJOBLOG	P000000262	QSYSOPR	12/10/04	16:45:34	ł *
2958	Selected	QPJOBLOG	P000000263	QSYSOPR	12/10/04	16:45:34	ł *
2957	Selected	QPJOBLOG	P00000264	QSYSOPR	12/10/04	16:45:34	ł *
2956	Selected	QPJOBLOG	P000000261	QSYSOPR	12/10/04	16:45:23	} *
						More	· · ·
F3=Exit	F5=Refres	h F9=Reve	rse F10=E:	rrors only	F11=All		
F12=Cancel	F13=Repea	t F17=Top	F18=B0	ottom			

Parameters

OPTION

Option

Determines what type of information is displayed initially.

***UNPRC** (default). All unprocessed transactions are displayed. Transactions which have been deleted or which completed normally are not displayed. *ALL. All available transactions are displayed irrespective of status.

*ERROR. Transactions where an error has occurred are displayed.

The program displays a list of transactions selected according to the OPTION parameter.

Options

Options that can be input against entries in the list are:

1=Resubmit	Resubmit the transaction.
	If a transaction has not been fully processed because of an error, this option allows you to tell CoolSpools Spool Admin to retry the transaction.
	When an error occurs during the processing of a transaction, and that error is not ignored (because it was included in the list of errors to be ignored on the IGNMSGID parameter of the CRTSPLRUL, ADDSPLSCPE commands etc.), CoolSpools Spool Admin will flag the transaction, and the transaction rule step in relation to which the error occurred, as being "in error".
	Transactions that are flagged as being "in error" will not be retried until you tell CoolSpools Spool Admin to do so by selecting option 1 against them in this list. This will remove the error flag and make the transaction available for processing.
	Processing of the transaction will restart from the first transaction rule step which was not successfully processed already.
4=Delete	Delete the transaction.
	Once deleted, the transaction cannot be processed. Only select this option if you are sure that you do not wish to process the spooled file concerned (for example, if the spooled file itself is no longer in the system).
5=Display	Display the transaction.
	Details of the spooled file transaction, including its origin, status and any rules selected to be processed are shown.
8=Errors	Display errors.
	Details of the errors that have occurred while processing the spooled file transaction are shown.
CoolSpools Spool Admin User Guide V6R1	Page: 74

Function keys

Available function keys are:

E Mala a su Rasida a
Exit the application.
Refresh the list.
Toggles the display between showing transactions in ascending chronological order and descending chronological order.
When displaying unprocessed transactions or all transactions, switches to showing errors only.
When displaying transactions in error, switches to showing unprocessed transactions.
When displaying unprocessed transactions or all transactions, switches to showing errors only.
When displaying all transactions, switches to showing unprocessed transactions.
When displaying unprocessed transactions or transactions in error, switches to showing all transactions.
Return to the previous screen.
Repeat an option to the end of the list.
Position the display to the top of the list
Position the display to the bottom of the list

Positioners

Or

The display can be positioned using the following positioner fields:

Position to date/time	Enter either a date or a date and a time to position the list to the first transaction where the transaction creation date is:		
	 Greater than or equal to the given date/time (if the list is in ascending order) 		
	 Less than or equal to the given date/time (if the list is in descending order) 		
Position to transaction	Enter a transaction number to position the list to the first entry where the transaction number is:		

- Greater than or equal to the given number (if the list is in ascending order)
- Less than or equal to the given number (if the list is in descending order)

Data

The "**Total**" displayed at the top of the screen is the current number of transactions in the system of the type selected, i.e. transactions in error, unprocessed transactions or all transactions.

The data displayed in the list is as follows:

Transaction number	The unique identifier for the spooled file transaction.	
Status	The status of the spooled file transaction.	
	Values are:	
	 Received. The data queue message related to the spooled file in question has been received and a transaction created. 	
	 Selected. CoolSpools Spool Admin has selected the rules to be processed but has not yet fully executed those rules. 	
	 Completed. Processing has completed normally. 	
	 Deleted. The transaction has been manually deleted and will not be processed. 	
Splf Name	The name of the spooled file to which the transaction relates.	
Job Name	The name of the job which created the spooled file to which the transaction relates.	
User	The name of the user profile which created the spooled file to which the transaction relates.	
Creation date/time	The date and time the spooled file transaction was created.	
Busy	A flag indicating whether the spooled file is currently being processed.	
	* = Busy. Blank = not busy.	
Error	A flag indicating whether processing of the spooled file generated errors which have not been cleared.	
	* = Errors exist. Blank = no errors exist.	

Available function keys are:

F3=Exit	Exit the application.
F5=Refresh	Refresh the list.
F12=Cancel	Return to the previous screen
F13=Splf attr	Displays the attributes of the spooled file.
F14=Splf job	Displays the job that created the spooled file.
F15=Proc job	Displays the job that is processing or most recently processed the spooled file transaction.

Transaction Details

When option 5=Display is selected against a spooled file transaction in the list, the Transaction Details screen is shown.

The screen displays the following information.

Transaction number	The unique identifier for the spooled file transaction.	
Transaction status	The status of the spooled file transaction.	
	Values are:	
	 Received. The data queue message related to the spooled file in question has been received and a transaction created. 	
	 Selected. CoolSpools Spool Admin has selected the rules to be processed but has not yet fully executed those rules. 	
	 Completed. Processing has completed normally. 	
	 Deleted. The transaction has been manually deleted and will not be processed. 	
Splf name/job/number	The name of the spooled file to which the transaction relates.	
	The details of the job which created the spooled file to which the transaction relates.	
	The number of the spooled file to which the transaction relates.	
Trns creation date/time	The date and time the spooled file transaction was created.	
Dtaq msg received date/time	The date and time the data queue message was received.	
Transaction created by job	The details of the job that created this transaction.	
Processing started date/time	The date and time processing of the transaction started. If this transaction has been processed	

	more than once, this is the most recent occasion on which processing started.
Processing ended date/time	The date and time processing of the transaction ended. If this transaction has been processed more than once, this is the most recent occasion on which processing ended.
	The screen also shows the number of seconds that elapsed between the start and end of processing.
Last processed by job	The job which processed the transaction. If this transaction has been processed more than once, this is the job which processed the transaction most recently.

If rules have been selected to be processed, the screen also lists the transaction rule steps that will be processed or have been processed, and the order in which they will be processed or have been processed.

The list includes:

Seq. Nbr.	The sequence number of the transaction rule step.		
	This consists of two parts. The first part is derived from the rule priority. The second part is a sequential allocated number which distinguishes between actions generated by the same rule. Together they determine the order in which actions are applied to the spooled file.		
Rule	The name of the rule which has been selected.		
Script	The name of the script to be processed, if any.		
Seq	The sequence number of the script entry, if any.		
Status	The status of the transaction rule step.		
	Values are:		
	 Ready. The transaction rule step is ready to be processed but has not yet been processed. 		
	 Completed. The transaction rule step has been processed without errors. 		
	 Error. One or more errors occurred during the processing of the transaction rule step. 		
	 Ignored. This transaction rule step has not been processed because a previous transaction rule step completed without error and the NOERRACN attribute was set top *STOP. 		
Deleted The transaction has be			

Deleted. The transaction has been manually deleted and will not be processed.

The date and time processing of this transaction rule step started, on the most recent occasion.

Entering a 5 against an entry in the list displays the details of the rule step. Information shown includes:

Trans. Nbr	The transaction number
Sequence Nbr.	The sequence number of the transaction rule step.
	This consists of two parts. The first part is derived from the rule priority. The second part is a sequential allocated number which distinguishes between actions generated by the same rule. Together they determine the order in which actions are applied to the spooled file.
Status	The status of this transaction rule step.
Proc. Started	The date and time processing of the rule step started, on the most recent occasion.
Proc. Ended	The date and time processing of the rule step ended, on the most recent occasion.
Proc. Time	The total time required to process the step, in seconds.
Rule name	The name and description of the rule which was selected to created the rule step.
Script	The name and description of the script which was being run as part of this rule step (if any).
Script entry	The name and description of the script entry which was being run as part of this rule step (if any).
Command string	The command string that was executed. This is the final command string after replacement of substitution variables and after conversion of option codes to command strings.

Transaction Error Details

When option 8=Errors is selected against a spooled file transaction in the main list, the Transaction Error Details screen is shown.

The screen displays the following information.

Transaction number	The unique identifier for the spooled file transaction.
Spooled file name	The name of the spooled file to which the transaction relates.
Spooled file job	The details of the job which created the spooled file to which the transaction relates.

The number of the spooled file to which the transaction relates.

The screen then shows a banner indicating how many errors exist in total and the number in the set of errors of the details shown in the latter part of the screen. Where more than one error exists, pressing Enter displays the next error.

Error number	The unique identifier of the error.
Error reported by job	The details of the job which reported the error.
Error reported at date/time	The date and time that the error was reported.
Error context	The rule number and sequence number that was being processed when the error occurred. If a script was being run, the script name and script entry number are also shown.
Error message id	The message identifier associated with the error.
Error message text	The text associated with the error message.

Other commands for working with transactions

As well as using the **WRKSPLTRN** command to work with transactions, you can also use the following transaction-related commands.

CRTSPLTRN (Create Spooled File Transaction)

This command can be used to generate a spooled file transaction for a spooled file.

It is intended to be used primarily in two sets of circumstances:

- **System initialization**. You can use CRTSPLTRN to import existing spooled files into CoolSpools Spool Admin for processing when the system is first being set up. Spooled files which were created prior to the installation of CoolSpools Spool Admin can be brought into the system this way.
- **Spooled files created with a "held" status.** CoolSpools Spool Admin transactions are only created automatically for spooled files which are created with a "ready" status. If your spooled files are created with a "held" status, they can be brought into CoolSpools Spool Admin periodically using this command.

CRTSPLTRN imports a single spooled file into CoolSpools Spool Admin. In order to import a batch of spooled files into CoolSpools Spool Admin, use RUNSPLFCMD along with CRTSPLTRN.

For example, the following command would select all spooled files on output queue QPRINT created in the last 7 days with a status of "held" and would run CRTSPLTRN to import the spooled file into CoolSpools Spool Admin.

RUNSPLFCMD USER(*ALL) OUTQ(QPRINT) AGERANGE(0 7) STATUS(*HELD) CMD(CRTSPLTRN SPLFNAME(*SLT) JOB(*SLT) SPLNBR(*SLT)) ERRACN(*CONTINUE)

Note the use of **ERRACN(*CONTINUE)** : this ensures that if an error occurs (e.g. if the spooled file is already in CoolSpools Spool Admin), processing continues and the error is ignored.

Parameters

SPLFNAME

Spooled file name

The name of the spooled file to be imported.

The special value ***SLT** should be used only when CRTSPLTRN is being run from within another CoolSpools Spool Admin function (e.g. WRKSPLFPPDM, or RUNSPLFCMD). It indicates that the CRTSPLTRN command should use the name of the currently selected spooled file.

JOB

Job

CoolSpools Spool Admin User Guide V6R1 www.ariadnesoftware.co.uk The qualified name of the job that created the spooled file.

The special value ***SLT** should be used only when CRTSPLTRN is being run from within another CoolSpools Spool Admin function (e.g. WRKSPLFPPDM, or RUNSPLFCMD). It indicates that the CRTSPLTRN command should use the details of the job that created the currently selected spooled file.

RPTMODE

Reporting mode

Whether this command should send a completion message when the command completes normally. Since this command is often used (in conjunction with WRKSPLFPDM or RUNSPLFCMD) to carry out a mass import of spooled files into CoolSpools Spool Admin , having the command send a message for each spooled file can cause a large number of messages to be sent to the joblog. You can avoid this by specifying RPTMODE(*QUIET).

*VERBOSE (default) = a completion message is sent.

*QUIET = no completion message is sent.

DLTSPLTRN (Delete Spooled File Transaction)

This command can be used to delete both processed and (optionally) unprocessed spooled file transactions. It provides a database purge facility.

Parameters	
USER	User
	The USER (User) parameter allows you to select spooled file transactions based on the user profile of the user who created the corresponding spooled file.
	Possible values are:
	*CURRENT (Default) Only files created by the user running this command are selected.
	*ALL Files created by all users are selected.
	user-name Specify a user name. Only files created by that user name are selected.
SPLFNAME	Spooled file name
	The name of the spooled file whose transactions are to be deleted.
AGERANGE	Age Range
	The age range parameter allows you to select spooled file transactions based on the creation date of the corresponding spooled file.
	Possible values are:
	*ALL (Default) Spooled files are selected irrespective of how long ago they were created.
	* MIN The value *MIN for the "from" element of the range indicates that there is no lower limit for the age range, i.e. that spooled files will be included so long as they are more recent than the upper limit.
	*MAX The value *MAX for the "to" element of the range indicates that there is no upper limit for the age range, i.e. that spooled files will be included so long as they are older than the lower limit.
	age_range Enter an age range in days. Spooled files are selected based on their creation date. If the current date minus the creation date falls in this range of days, the spooled file will be selected. The calculation of the number of days is based on the date alone and takes no account of the time.
	D

CoolSpools Spool Admin User Guide V6R1 www.ariadnesoftware.co.uk Page: 83

For example, a spooled file created one minute before midnight on one day will be considered to be one day old if processed by CoolSpools Spool Admin one minute after midnight (i.e. only two minutes later).

DLTUNPRC Delete unprocessed

Whether unprocessed transactions should be deleted.

***NO** (default) = Do no delete unprocessed transactions.

***YES** = Delete unprocessed transactions.

Reorganize physical files

Whether CoolSpools Spool Admin should try to reorganize your physical files after processing deletions.

*NO (default) = Do no reorganize physical files.

***YES** = Reorganize physical files.

Note that reorganizing files could take a significant amount of time to complete if you have many records in the file. The system will be unavailable while reorganization is in progress. You must ensure that sufficient time is available for the reorganization to complete.

If you are planning to delete several sets of records, specify RGZPFM(*NO) for all but the last set.

RGZPFM

WRKTRNSTS (Work with Transaction Status)

The **WRKTRNSTS** (Work with Transaction Status) command displays a summary of the current processing position and provides some basic statistics.

ARIADNE1	CoolSp	ools Spool Ad	min V2R1M0 -	Transaction Stat	cus
Control job Monitors active :			—		
		Transaction	Volumes		
Total :	4830	Unprocessed :	521	In error . :	7
		Transaction	Statistics -		
	Last	1-24	24-48	48-96	96-168
	Hour	hrs ago	hrs ago	hrs ago	hrs ago
Created :	38	3192	6	1594	0
Nbr of pages :	2158	0	0	0	0
Data size (Mb):	3.4	0.0	0.0	0.0	0.0
Processed :	0	2709	6	1593	0
Unprc no error:	38	476	0	0	0
In error :	0	7	0	0	0
Deleted :	0	0	0	1	0
Avg. time (s) :	0.000	87.361	4.295	13.965	0.000
F3=Exit F5=Rei	fresh	F12=Cancel	F15=Work	with jobs	
F18=Work with trans	sactions	F21=Command	line		

Function keys

Available function keys are:

F3=Exit	Exit the application.
F5=Refresh	Refresh the list.
F12=Cancel	Return to the previous screen.
F15=Work with jobs	Runs WRKACTJOB SBS(sbsd_name), where sbsd_name is the name of the subsystem in which

CoolSpools Spool Admin User Guide V6R1 www.ariadnesoftware.co.uk Page: 85

	the control job is running. This provides a convenient way of checking the various CoolSpools Spool Admin jobs that are running.
F18=Work with transactions	Runs WRKSPLTRN to allow you to view and work with transactions at a detailed level. Initially, only unprocessed transactions are displayed.
F21=Command line	Provides a command line.

Data

The data displayed is as follows:

Control job	The name, user and number of the current or most recent CoolSpools Spool Admin control job.
Status	The status of the current or most recent control job.
Monitors active	The number of currently active monitor jobs.
Monitors defined	The number of monitors which are defined.
	Normally, the number of active monitor jobs and the number of monitors defined should be the same. If these numbers differ, this could be because a new monitor has recently been defined, or an old monitor deleted, and the spooled file jobs have not been restarted since. Alternatively, it could indicate a problem with a monitor job.
Processors active	The number of processor jobs currently active.
	If this number is zero, no spooled file will be processed. Too low a number could result in poor throughput.
Ī	ransaction Volumes
Total	The total number of transactions in the system. If this number is high (e.g. in excess of 10,000), you should consider running DLTSPLTRN to delete unwanted processed transactions.
Unprocessed	The number of transactions which have not been processed. This includes both transactions not yet processed and those where processing was attempted but could not be completed due to an error.

The number of transactions where processing was attempted but could not be completed due to an error.

Transaction Statistics

The statistics display the numbers of transactions falling into different categories according to 5 different time periods:

- Transactions created in the last hour
- Transactions created between 1 and 24 hours ago
- Transactions created between 24 and 48 hours ago
- Transactions created between 48 and 96 hours ago
- Transactions created between 96 and 168 hours ago

Created	The total number of transactions created in the time period.
Nbr of pages	The number of pages in the spooled files associated with the transactions counted in the above total.
Data size (Mb)	The data size in Megabytes of the spooled files associated with the transactions counted in the above total.
Processed	Of the total created in the time period, how many have been successfully processed.
Unprc. no error	Of the total created in the time period, how many have not yet been processed, but not because an error occurred.
In error	Of the total created in the time period, how many have not yet been processed because an error occurred.
Deleted	Of the total created in the time period, how many have been manually deleted (using WRKSPLTRN option 4)
Avg. time (s)	The average time taken to complete processing of a transaction in the time period, measured in seconds.

Substitution variables

When you create a user-defined option, you can include substitution variables. The following substitution variables are recognized by CoolSpools Spool Admin and are converted at run time as shown below.

For example, you could define an option PD to run CoolSpools CVTSPLPDF command to convert spooled files to PDF format with a particular set of parameters:

PD = CVTSPLPDF	FROMFILE(&F) TOSTMF(&F_&D_&T.&X) JOB(&N/&U/&J) SPLNBR(&S) STMEOPT(*REPLACE)
	STMFOPT(*REPLACE)

When this option is selected against a spooled file, CoolSpools Spool Admin will replace the substitution variables as per the table below. The TOSTMF parameter specifies that the stream file that is created should be the spooled file name followed by an underscore, then the creation date of the spooled file, another underscore, then the creation time of the spooled file, a period and the extension appropriate for PDF (PDF).

Substitution Variable	At run time, CoolSpools Spool Admin replaces the variable with
&A	The user data attribute of the spooled file
&B	Number of copies attribute of the spooled file
&C	Product library of the command. For example, &C/CVTSPLPDF converts to COOLSPV6R1/CVTSPLPDF.
&D	The date the spooled file was created. The format of this date is determined by the date format attribute of the job running the command.
&E	The email address of the user that created the spooled file, as derived from the system distribution directory
&F	The name of the spooled file.
&G	Form type of the spooled file
&H	(Currently unused)
&I	The current user profile
&J	The name of the job that created the spooled file
&K	The message key of the current spooled file message (if the spooled file is waiting for a message to be replied to)

CoolSpools Spool Admin User Guide V6R1 www.ariadnesoftware.co.uk

&L	(Currently unused)
&M	The name of the user who created the spooled file, as derived from the system distribution directory.
&N	The job number of the job that created the spooled file
&O	The user profile which owns the spooled file.
&P	The printer device to which the spooled file is allocated.
&Q	The output queue where the spooled file is currently located.
&R	The output queue library.
&S	The spooled file number
&Т	The time the spooled file was created in *HMS format (HHMMSS).
&U	The user of the job that created the spooled file
&V	The message queue associated with the writer to which the spooled file is currently allocated.
&W	The library of the message queue associated with the writer to which the spooled file is currently allocated.
&X	The file extension appropriate to the file format selected, e.g. PDF for TOFMT(*PDF), XLS for TOFMT(*XLS), TXT for TOFMT(*TEXT) etc.
&Y	Date spooled file was opened in YYYYMMDD format
&Z	User-defined data of the spooled file

CoolSpools Spool Admin Log File

Logging of spooled file options is activated if you specify LOG(*JOBTYPE) (the default) when you run WRKSPLFPDM in batch mode, or if you specify LOG(*YES) and run WRKSPLFPDM in either batch or interactive mode.

Spooled files processed by spooled file monitors and processing jobs are not logged in the CoolSpools Spool Admin log file since similar information is available from the CoolSpools Spool Admin spooled file transactions file ST_SPLTRN.

When the logging of spooled file options is active, *CoolSpools Spool Admin* writes a record to the log file **ST_SPLLOG** for every option it processes against a spooled file. This can be useful for a variety of purposes:

- As a permanent audit trail of actions taken against spooled files
- To drive subsequent processing. For example, an archiving application might decide whether to delete a spooled file by first checking the log file to ensure that the spooled file was successfully saved
- As a source of statistics

Each log record represents an option processed against a spooled file by the WRKSPLFPDM command.

Each log record contains the following information:

Field Name	Field Type	Description
SPLFNAME	CHAR(10)	The name of the spooled file to which the option
		was applied.
SPLFJOB	CHAR(10)	The name of the job in which the spooled file was
		created.
SPLFUSER	CHAR(10)	The user who created the spooled file.
SPLFJOBNBR	CHAR(6)	The number of the job in which the spooled file was
		created.
SPLFSPLNBR	BINARY(4)	The spooled file number in the job.
SPLFJOBID	CHAR(16)	The system internal identifier for the job in which the
		spooled file was created.
SPLFINTID	CHAR(16)	The system internal identifier for the spooled file.
OPTION	CHAR(2)	The option processed.
OPTTIME	TIMESTAMP	The date and time at which processing of the option
		completed.
OPTJOB	CHAR(10)	The name of the job in which the option was
		processed.
OPTUSER	CHAR(10)	The user name of the job in which the option was
		processed.
OPTJOBNBR	CHAR(6)	The number of the job in which the option was
		processed.
OPTRESULT	CHAR(1)	Whether processing completed successfully or not.
		1=Ended without error. 0=Ended in error.