

Installation Guide

Version V6R1M0 2010

Table of Contents

Choosing your installation method	З
Method A.	
Automated install from a PC	
Summary	
Prerequisites	
Downloads	
Instructions	7
Method B	17
Automated install from a PC and the system i	17
Summary	
Prerequisites	
Downloads	17
Instructions	17
Method C	27
Manual installation of the installer, automated installation from the system i	27
Summary	
Prerequisites	
Downloads	
Instructions	
Method D.	
Manual installation on the system i	
Summary	
Prerequisites	
Downloads	
Instructions	

Choosing your installation method

There are several ways in which CoolSpools V6R1M0 can be installed. Which method is best for you depends on a number of factors. Choose your preferred method from the list below and click on the link to follow the instructions for that method.

Method	Overview	Description	Pr	erequisites
A	Automated install from a PC	This method involves running a .EXE file (self-extracting zip) file on your PC to install CoolSpools on your system i. Depending on which .EXE	a)	You must sign on to the system i as a user with *SECADM and *ALLOBJ special authorities.
		program you run, you can either install the entire CoolSpools package or individual product options.	b)	Either an FTP (preferred) or System i Access connection to the system i from your PC.
		The PC installer will send the code to be installed to the system i and run the commands needed to install CoolSpools there.	c)	You must be willing and able to open up your PC firewall so the installer can
		Note that CoolSpools does not need a PC and after installation all CoolSpools functionality runs entirely on the system i.		communicate between your PC and the system i.
		Select this method if you are more comfortable running things from a PC.		
B	Automated install from a PC and the system i	This method involves running a .EXE file (self-extracting zip) file on your PC to install just a small installer application on the system i.	a)	You must sign on to the system i as a user with *SECADM and *ALLOBJ special authorities.
		The rest of the installation, including downloading of the install files, is then carried out on the system i itself.	b)	Either an FTP (preferred) or System i Access connection to the system i from your
		Note that CoolSpools does not need a PC and after installation all CoolSpools functionality runs entirely on the system i.	c)	and able to open up your PC firewall so the
		Select this method if you prefer to run things mostly from the system i.		installer can communicate between your PC and the

				system i.
			d)	An internet connection must be available for use from the system i so that the installer can connect to ariadne's web server via FTP to download the install files.
<u>C</u>	Manual installation of the installer, automated installation from the	Select this method if you cannot use the PC install programs used by methods A and B above, for example if you cannot open up your PC firewall to all the installer to connect to the system i		You must sign on to the system i as a user with *SECADM and *ALLOBJ special authorities. An FTP connection
	system i	 e system i. bu will manually install the nall installer application on the stem i then run an automated stall of the rest of the splication from the system i elf. elect this method only if it is from your PC to system i to allow transfer of the s files for the smaller application from the system i elf. 	from your PC to the system i to allow transfer of the save files for the small installer application.	
D	Manual installation mainly on the system i	Select this method only if it is not possible to use any of the above methods for some reason, as it is more complex than the others.	a)	You must sign on to the system i as a user with *SECADM and *ALLOBJ special authorities.
		You are required to download one or more zip files each containing one or more system i save files, Those save files must be unzipped and transferred to the system i. You must then run a series of Restore Licensed Program (RSTLICPGM) commands to install the product options you want.	b)	An FTP connection from your PC to the system i to allow transfer of the save files.

Method A

Automated install from a PC

Summary

This method involves running a program on your PC to install the entire CoolSpools package or individual product options on your system i.

Depending on which program you run, you can either install the entire CoolSpools package or individual product options.

The PC installer will send the code to be installed to the system i from your PC and run the commands needed to install CoolSpools there.

Note that CoolSpools does not need a PC and after installation all CoolSpools functionality runs entirely on the system i.

Select this method if you are more comfortable running things from a PC.

Prerequisites

- a) You must sign on to the system i as a user with *SECADM and *ALLOBJ special authorities.
- b) Either an FTP (preferred) or System i Access connection to the system i from your PC must be available.
- c) You must be willing and able to open up your PC firewall so the installer can communicate between your PC and the system i.

Downloads

In order to install CoolSpools using this method, you must first download and run the appropriate .EXE file from the list below.

All files can be downloaded from http://www.ariadnesoftware.co.uk

Product Option	Option Name	.EXE file name
All options	Complete Package	CoolSpoolsAllOptionsSetup.EXE
Installs the o	complete CoolSpools	package on your system i.
No other Co	olSpools setup is req	uired once this program has completed.

Product Option	Option Name	.EXE file name
*BASE	Base Option	CoolSpoolsBaseSetup.EXE

Installs just the CoolSpools Base option on your system i.

The Base option must be installed before any of the other product options below can be installed.

CoolSpools Installation Guide V6R1

Once this program has completed, you must install the individual options that you wish to use by running one or more of the programs listed below.

Product Option	Option Name	.EXE file name
1	Spool Converter	CoolSpoolsSpoolConverterSetup.EXE
-	Spool Converter lets	Converter option on your system i. you convert system i spooled files to PDF, Excel
The Base of	ption must be installed	d before you can install other options.

Product Option	Option Name	.EXE file name
2	Email	CoolSpoolsEmailSetup.EXE
Installs just	the CoolSpools Email	option on your system i.
CoolSpools CoolSpools		emails from your system i and attach files that

The Base option must be installed before you can install other options.

Product Option	Option Name	.EXE file name
3	Spool Admin	CoolSpoolsSpoolAdminSetup.EXE
Installs just	the CoolSpools Spool	Admin option on your system i.
		manage spooled files on your system i and sing and distribution of spooled files as PDFs,

Excel etc.

The Base option must be installed before you can install other options.

Product Option	Option Name	.EXE file name
4	Database	CoolSpoolsDatabaseSetup.EXE

Installs just the CoolSpools Database option on your system i.

CoolSpools Database lets you extract information from on your system i database and publish it as Excel spreadsheets, XML, CSVs, text, HTML etc. Query and SQL output can also be saved in these formats.

The Base option must be installed before you can install other options.

Product Option	Option Name	.EXE file name
5	NetServer Toolkit	CoolSpoolsNetServerToolkitSetup.EXE

Installs just the CoolSpools NetServer Toolkit option on your system i.


CoolSpools NetServer Toolkit is a free component of the CoolSpools suite which provides a quick and easy way of creating and managing NetServer file and print shares. NetServer file shares are a great way of accessing PDFs, Excel spreadsheets and other files created by CoolSpools from your PC.

The Base option must be installed before you can install other options.

Instructions

When you download any of the files above, you will be given the option to run it or save it to your PC. Select Run to start the install process immediately. Select Save to store the installation program on your PC. If you choose save to it to your PC, in order to run it at a later time, locate it on your PC (using Computer, My Computer or Explorer) and double click it to start the installation process.

You will first see this welcome screen or something very similar:



Click Next.

The following screen explains what part of the software is being installed and reminds you of the instructions explained below.

This program will install the full CoolSpools suite on your system i (iSeries, AS/400). On the next screen you will be asked to confirm acceptance of the license agreement. After that, we strongly recommend you: 1. Select STANDARD install not custom install when offered the choice. 2. Use the second install option TCP/IP (FTP server) on the screen after that. Make sure your FTP server and host servers are running on your system i (use command STRHOSTSVR and STRTCPSVR *FTP).						
 Select STANDARD install not custom install when offered the choice. Use the second install option TCP/IP (FTP server) on the screen after that. Make sure your FTP server and host servers are running on your system i (use command STRHOSTSVR and STRTCPSVR) 	(iSeries, AS	/400). On the i	next screen y	ou will be asl		*
choice. 2. Use the second install option TCP/IP (FTP server) on the screen after that. Make sure your FTP server and host servers are running on your system i (use command STRHOSTSVR and STRTCPSVR	After that, w	e strongly rec	ommend you	C.		ш
	choice. 2. Use the s after that. M your system	econd install ake sure your	option TCP/I FTP server	P (FTP serve and host serv	r) on the screen ers are running c	'n

Read the text and click Next.

CoolSpools Installation Guide V6R1 www.ariadnesoftware.co.uk You are now given the opportunity to read the software license agreement that governs usage of the software.

icense Agreement Please read the following license agreement carefully.	
SOFTWARE LICENCE	*
WARNING. BEFORE PROCEEDING PLEASE READ THE TERMS OF THIS LICENCE AGREEMENT CAREFULLY. YOU MAY OBTAIN A COPY OF THIS SOFTWARE PRODUCT BY DOWNLOADING IT REMOTELY FROM OUR SERVER. ALL INTELLECTUAL PROPERTY RIGHTS IN THE PROGRAMS AND DATA WHICH CONSTITUTE THIS SOFTWARE PRODUCT ("THE SOFTWARE") ARE AND REMAIN THE PROPERTY OF THE LICENSOR. YOU ARE LICENSED TO USE THE SOFTWARE ON THE CONDITION	
 I accept the terms in the license agreement. I do not accept the terms in the license agreement. 	
	ancel

Read the text, and, if you are happy to accept it, click on the "I accept" option, then click Next.

On the next screen you are asked whether you wish to use the Standard or Custom install method.

CoolSpools Version 6 All Options - iInstall Wizard
Select An Installation Type You can choose to install all of the application, or just a portion.
Select the type of installation you want to perform. Standard installation will install all the components of the applicaiton. In order to select what to install, select the Custom type of installation.
 Standard Custom
iInstall Kack Next > Help Cancel

The Custom install method is intended for use only in special circumstances and you should not select this option unless instructed to do so by ariadne support to overcome an installation problem.

Select "Standard" if not already selected, and click Next.

CoolSpools Version 6 All Options - il	nstall Wizard	
Select protocol Select the protocol to use when conner	cting to the iSeries.	
-@ -Use TCP/IP (FTP server)		
Host:		
Userid:		🔲 FTP Debug log
Password:]
Save setting for the next time ilnstal	l Wizard is run.	
Specify parameters to restore commeting the state of		
- Ba	ack Next >	Help Cancel

The only option is TCP/IP (FTP server).

In order to connect to your system i using FTP, the FTP server must be started on your system i. If this is not already running, you can start it with

STRTCPSVR SERVER(*FTP)

Fill in the following:

Host:

Specify the name or IP address of the system i on which you wish to install the software.

User id:

Specify the user profile with which you will sign on to the system i. This must be a user profile with *SECADM and *ALLOBJ special authorities, e.g. QSECOFR.

Password:

Specify the password for the user profile above.

The other fields are optional:

Save setting...

Check this box if you want the installer to remember your details for the next time you run an installation.

FTP debug log

Check this box to generate a log of the FTP commands that are executed.

Only use this option if requested to do so by ariadne support.

Specify parameters to restore commands:

Check this box to specify additional restore parameters.

Only use this option if requested to do so by ariadne support.

Note the software can only be restored to the System ASP

Click Next.

You will now be shown a screen that gives you the chance to confirm that everything is ready for the installation (for example, that you are connected to the system i).

The installation program has now all the information needed in order to install the application. Click on 'Next' to start the installation process.	Begin installation				
Click on 'Next' to start the installation process.	Are you ready?				
Click on 'Next' to start the installation process.					
stall	The installation pro	ogram has now all the inforr	nation needed in or	der to install the	application.
	Click on 'Next' to s	tart the installation process	2		
	Click on 'Next' to s	tart the installation process	2		
	Click on 'Next' to s	tart the installation process	2		
	Click on 'Next' to s	tart the installation process	2		
nstall	Click on 'Next' to s	tart the installation process			
	Click on 'Next' to s	tart the installation process			
		tart the installation process	2		

Please note that the install process may take as much as 45 minutes to complete when the option to install the complete package is being run.

Click Next when ready to start.

You will see this screen or something very similar.

Installation in pro	gress application is in progress.	
	Preparing iSeries. One moment please.	
Estimated time k	eft: 00:17:39.	
istall —		

It is possible that at this point your PC firewall might display a message such as this indicating that the install program needs to be granted permission to communicate between your PC and the system i.

Wind	lows Security Alert	
۲	Windows Firew	all has blocked some features of this program
unblock		is program from accepting incoming network connections. If you nblocked on all private networks that you connect to. <u>What are</u> <u>n?</u>
4	Name:	iInstall
	Publisher:	Jesper Wachs
	Path:	C:\Windows\~ExeDist.3_NWSIN32.EXE
	Network location:	Private network
		What are network locations?
		Keep blocking Unblock

If you see a message such as this, select Unblock or whatever your firewall's equivalent option is to allow the program to communicate with the system i.

If your firewall simply blocks the link without allowing you the option to unblock it, the installer will fail. Port 20 must be open to allow the installer to communicate with the

CoolSpools Installation Guide V6R1

www.ariadnesoftware.co.uk

system i using FTP. If it is not possible to open up the firewall, use either Install Method C or Install Method D instead.

If the connection is successful, you will now see screen similar to the following while the objects are copied to your system i and the commands are run to carry out the installation:

nstallation in progress Installation of the application is in progress.	
Copying object 'CP_INSTALL/CPV6R10PT4(*FILE)'	
Estimated time left: 00:29:56.	

When the install process completes, you will see the following screen.

istallation has finished The objects has been installed.	
Thanks for installing CoolSpools.	*
To get started, enter the following command at a command line on your system i (iSeries, AS/400):	
GO COOLSPV6R1/COOLMENU	
Contact support@ariadnesoftware.co.uk if you need any assistance.	
You can use the software without a license key for 30 days. After that time, you'll need to contact sales@ariadnesoftware.co.uk to place an order to ask for a temporary license key to extend your trial.	Ŧ
tall-	1,1.2.1
📇 < Back Next > Help Ca	ancel

Read the instructions, then click Next to see the final screen.

Installing: CoolSpools Version 6 All Options The installation is finished The application has been installed	
The application is now installed using the options you chose. The a to be used.	application is now ready
iInstall	
< Back Next >	Help Finish

Click Finish to complete the installation.

Since nothing is installed on your PC, Windows may get confused and show a screen suggesting that the install failed.

CoolSpools Installation Guide V6R1 www.ariadnesoftware.co.uk

Program (Compatibility Assistant	23
This prog	ram might not have installed correctly	
	am didn't install correctly, try reinstalling using settin ible with this version of Windows.	igs that
	Program: Selfextracter	
	Publisher: Jesper Wachs	
_	Location: C:\Users\ariadne\AppDat\CoolSpoolsSe	tup[1].EXE
🖲 Reins	stall using recommended settings	
This	program installed correctly	
		Cancel
What se	ettings are applied?	

You can ignore this. Click "This program installed correctly" or equivalent.

If you ran the install program for the complete package (CoolSpools AllOptionsSetup.EXE), the entire CoolSpools package has now been installed and you can begin to use it by displaying the CoolSpools menu by running

GO COOLSPV6R1/COOLMENU

on your system i.

If you installed the CoolSpools Base option by running CoolSpoolsBaseSetup.EXE, you should now repeat the process for each individual product option you wish to install.

Alternatively, if you are able to install from the system i, you can just follow the procedure below for the base option and then use the "Install product options" option from the Base Option Menu. Display the base option menu by running:

GO COOLSPV6R1/BASEMENU

Method B

Automated install from a PC and the system i

Summary

This method involves running a small .EXE file (self-extracting zip) file on your PC to install just a small installer application on the system i. The rest of the installation, including downloading of the install files, is then carried out on the system i itself.

Note that CoolSpools does not need a PC and after installation all CoolSpools functionality runs entirely on the system i.

Select this method if you prefer to run things mostly from the system i.

Prerequisites

- a) You must sign on to the system i as a user with *SECADM and *ALLOBJ special authorities.
- b) Either an FTP (preferred) or System i Access connection to the system i from your PC.
- c) An internet connection must be available for use from the system i so that the installer can connect to ariadne's web server via FTP to download the install files.
- d) You must be willing and able to open up your PC firewall so the installer can communicate between your PC and the system i.

This method involves running a .EXE file (self-extracting zip) file on your PC to install just a small installer application on the system i. The rest of the installation, including downloading of the install files, is then carried out on the system i itself.

Downloads

In order to install CoolSpools using this method, you must first download and run the installer program CoolSpoolsSetup.EXE from All files can be downloaded from http://www.ariadnesoftware.co.uk

Instructions

On the PC

When you download the installer program CoolSpoolsSetup.EXE, you will be given the option to run it or save it to your PC. Select Run to start the install process immediately. Select Save to store the installation program on your PC. If you choose save it to your PC, to run it at a later time, locate it on your PC (using Computer, My Computer or Explorer) and double click it to start the installation process.

You will first see this welcome screen:



Click Next.

The following screen explains that you are installing just the Installer application and reminds you of the instructions explained below.

Introduction to the i		
(iSeries, AS/40) install process Select standard Use the secon that. Make sure system i (use c	vill install the CoolSpools installer on your system i D). Once this step is completed, the remainder of the takes place on your system i. d install not custom install when offered the choice. d install option TCP/IP (FTP server) on the screen afte your FTP server and host servers are running on your ommand STRHOSTSVR and STRTCPSVR*FTP). t@ariadnesoftware.co.uk if you need any assistance	

Read the text and click Next.

CoolSpools Installation Guide V6R1 www.ariadnesoftware.co.uk On the next screen you are asked whether you wish to use the Standard or Custom install method.

CoolSpools Version 6 All Options - iInstall Wizard	
SOFTWARE LICENCE	
WARNING. BEFORE PROCEEDING PLEASE READ THE TERMS OF THIS LICENCE AGREEMENT CAREFULLY. YOU MAY OBTAIN A COPY OF THIS SOFTWARE PRODUCT BY DOWNLOADING IT REMOTELY FROM OUR SERVER. ALL INTELLECTUAL PROPERTY RIGHTS IN THE PROGRAMS AND DATA WHICH CONSTITUTE THIS SOFTWARE PRODUCT ("THE SOFTWARE") ARE AND REMAIN THE PROPERTY OF THE LICENSOR. YOU ARE LICENSED TO USE THE SOFTWARE ON THE CONDITION	.
 I accept the terms in the license agreement. I do not accept the terms in the license agreement. 	
	ancel

The Custom install method is intended for use only in special circumstances and you should not select this option unless instructed to do so by ariadne support to overcome an installation problem. Select "Standard" if not already selected, and click Next.

You are now given a choice of communications protocols. The installer will use the protocol selected to communicate with your system i to transfer the installation files and run the necessary commands.

🕤 -Use Client Access/400® —	14	
iSeries to install on:	192.168.0.14	-
Enter userid/password:	ARIADNE	
•Use TCP/IP (FTP server) – Host:	192.168.0.14	
Userid:	ARIADNE	FTP Debug lo
Password:	******	
ave setting to the next time il	to a table of the second	

The options are Client Access/400 and TCP/IP (FTP server). We strongly recommend that you select the second option **TCP/IP (FTP server)** unless instructed by ariadne support to use the other method for some reason.

In order to connect to your system i using FTP, the FTP server must be started on your system i. If this is not already running, you can start it with

STRTCPSVR SERVER(*FTP)

Fill in the following:

Host:

Specify the name or IP address of the system i on which you wish to install the software.

User id:

Specify the user profile with which you will sign on to the system i. This must be a user profile with *SECADM and *ALLOBJ special authorities, .e.g. QSECOFR.

Password:

Specify the password for the user profile above.

The other fields are optional:

Save setting...

Check this box if you want the installer to remember your details for the next time you run an installation.

FTP debug log

Check this box to generate a log of the FTP commands that are executed.

Only use this option if requested to do so by ariadne support.

CoolSpools Installation Guide V6R1

Specify parameters to restore commands:

Check this box to specify additional restore parameters.

Only use this option if requested to do so by ariadne support.

Click Next.

You will now be shown a screen that gives you the chance to confirm that everything is ready for the installation (for example, that you are connected to the system i).

Begin installation Are you ready?		
	ogram has now all the information needed in or tart the installation process.	rder to install the application.

Click Next when ready to start.

It is possible that at this point your PC firewall might display a message such as this indicating that the install program needs to be granted permission to communicate between your PC and the system i.

Wind Wind	dows Security Alert		
		all has blocked some features of this program	
unblock		is program from accepting incoming network connections. If you nblocked on all private networks that you connect to, <u>What are</u> <u>n?</u>	
2	Name:	iInstall	
\triangleleft	Publisher:	Jesper Wachs	
	Path:	C:\Windows\~ExeDist.3_NWSIN32.EXE	
	Network location:	Private network	
		What are network locations?	
		Keep blocking Unblock	

If you see a message such as this, select Unblock or whatever your firewall's equivalent option is to allow the program to communicate with the system i.

If your firewall simply blocks the link without allowing you the option to unblock it, the installer will fail. Port 20 must be open to allow the installer to communicate with the system i using FTP. If it is not possible to open up the firewall, use either Install Method C or Install Method D instead.

If the connection is successful, you will now see a screen similar to the following while the objects are copied to your system i and the commands are run to carry out the installation:

Installing: CoolSpools Version 6 Installer	
Installation in progress Installation of the application is in progress.	
Copying object 'CP_INSTALL/CP_INSPRDR(*PGM)'.	
Estimated time left: 00:16:15.	
- iInstall < Back Next > Help	Cancel

When the install process completes, you will see the following screen.

nstallation ha The objects l	as finished nas been installed.	
	r installing the CoolSpools installer. You can now proceed It the remainder of the install process on your system i S/400).	•
	your system i (iSeries, AS/400) as a user with *SECADM 0BJ authority and run the following command:	111
CP_INST/	ALL/INSTALL.	
Contact su	pport@ariadnesoftware.co.uk if you need any assistance.	
You can u	se the software without a license key for 30 days. After that	•
tall ———		

Read the instructions, then click Next to see the final screen.

CoolSpools Installation Guide V6R1 www.ariadnesoftware.co.uk

Installing: CoolSpools The installation is fini: The application has be	shed
The application is now to be used.	installed using the options you chose. The application is now ready
ilnstall —	< Back Next > Help Finish

Click Finish to complete the installation.

Since nothing is installed on your PC, Windows may get confused and show a screen suggesting that the install failed. You can ignore this. Click "This program installed correctly" or equivalent.

Program Compatibility Assistant
This program might not have installed correctly
If this program didn't install correctly, try reinstalling using settings that are compatible with this version of Windows.
Program: Selfextracter Publisher: Jesper Wachs Location: C:\Users\ariadne\AppDat\CoolSpoolsSetup[1].EXE
Reinstall using recommended settings
This program installed correctly
Cancel
What settings are applied?

On the System i

Now go to your system i command line and type this command and press Enter.

CP_INSTALL/INSTALL

This starts the next stage of the install process, which downloads and installs the actual CoolSpools product code on your system i.

N.B.

If you receive an error message about a signature violation, then you probably have a CoolSpools V5 library in the system portion of your library list. DSPLIBL to view your library list. If either CVTSPLV5R1 or COOLSPV5R1 is shown, remove them with RMVLIBLE, EDTLIBL or CHGSYSLIBL.

You will see a screen like this:

Co	oolSpools - Install Options Serial nbr : 65-772FF LPAR 001	
Select the product options to install by enter Y=Yes or N=No below.		
*BASE Base option Y *NOTINSTALLED	Base code and shared functions. Must be installed before any other options.	
<pre>1. Spool converter Y *NOTINSTALLED</pre>	Convert spooled files to PDF, Excel, XML, HTML, text etc. Split spooled files. Combine PDFs.	
2. Email Y *NOTINSTALLED	Send emails using a simple command or an API. Attach PDFs, Excel files or other files types.	
<pre>3. Spool admin Y *NOTINSTALLED</pre>	Manage spooled files online or in batch. Set up automatic processing and distribution rules.	
4. Database Y *NOTINSTALLED	Convert database files and save SQL and query output as Excel, XML, CSV, HTML or text.	
5. NetServer Toolkit Y *NOTINSTALLED	An easy and convenient way of managing NetServer and access PDFs etc from your PC. FREE!	
F3=Exit F10=Install inter	actively F12=Cancel F19=Install in batch	

Select the options you wish to install by entering Y=Yes or N=No against them. The base option is mandatory and cannot be deselected if it is not currently installed.

When you are ready to install, press F10 if you wish to install the software interactively, or F19 to install in batch.

CoolSpools Installation Guide V6R1

If you press F19, you will be prompted with a SBMJOB command which will give you an opportunity to change the job queue or any other job parameters that might need to be modified from the defaults. The command string to be run and the current library are set automatically and cannot be modified.

The install library CP_INSTALL can be deleted once you have finished installing.

Method C

<u>Manual installation of the installer, automated installation</u> from the system i

Summary

This method involves running a series of commands on your PC and on the system i to install the installer application on system i. The rest of the installation, including downloading of the install files, is then carried out on the system i itself as per Method B above.

Note that CoolSpools does not need a PC and after installation all CoolSpools functionality runs entirely on the system i.

Select this method if you prefer to run things mostly from the system i and are unable to use the CoolSpoolSetup.EXE file to install the installer application for some reason (for example if you cannot modify your firewall to allow it to connect to the system i).

Prerequisites

- a) You must sign on to the system i as a user with *SECADM and *ALLOBJ special authorities.
- b) An internet connection must be available for use from the system i so that the installer can connect to ariadne's web server via FTP to download the install files.
- c) You must be able to use FTP to transfer data between your PC and the system i

Downloads

In order to install CoolSpools using this method, you must first download the install file for the installer application which is called CP_INSTALL.ZIP and save it to your PC.

Instructions

The zip file called CP_INSTALL.ZIP contains a file called CP_INSTALL.SAV which in turn contains the installer application that needs to be installed on the system i. The contents of the CP_INSTALL.SAV file must be transferred to a save file on the system i using FTP.

Transferring the CP_INSTALL.SAV file using FTP

This method uses FTP (File Transfer Protocol) to transfer the CP_INSTALL.SAV file from your PC to your system i. It is assumed that you have stored the CP_INSTALL.ZIP file which you downloaded from the Internet on your PC and that you have enabled an FTP link between your PC and your system i.

Steps to be carried out on the PC are shown in green.

Steps to be carried out on the system i are shown in blue.

a)

On your PC, choose an existing directory or create a new directory for CoolSpools installation, either within Computer (My Computer, Windows Explorer), or from the DOS prompt, e.g.:

md c:\CoolSpools

b)

On your PC, use WinZip. PKZIP etc. to extract the CP_INSTALL.SAV file from the zip file into the directory you created in (a) above.

Alternatively, open the zip file as a directory in Computer (My Computer, Windows Explorer) and copy the CP_INSTALL.SAV file to the directory you created in (a) above..

c)

On your system i, create a library called CP_INSTALL, e.g.

crtlib CP_INSTALL

then create a save file called CP_INSTALL in that library:

crtsavf CP_INSTALL/CP_INSTALL

d)

On your PC, start an FTP session to your system i. You may use FTP packages such as CuteFTP or simply go to the DOS prompt and type:

ftp AS400_name

where AS400_name is the name of your system i. You can also use the IP address rather than the system name.

You will be prompted to enter your user id and password. Please ensure that you sign on with a user id that has adequate authority. We recommend that you sign on as the Security Officer QSECOFR or another user profile with *SECADM and *ALLOBJ special authorities.

Issue the following FTP commands within the FTP session:

bin

This command instructs FTP not to carry out any conversion on the data to be sent to the system i.

quote site na 1

This makes sure the system i is using naming format 1 (path naming). This is important if your FTP attributes (CHGFTPA command NAMEFMT parameter) have the initial naming format set to *LIB (library/object naming) rather than *PATH (IFS path naming).

cd /QSYS.LIB/CP_INSTALL.LIB

This command makes CP_INSTALL the current library of the FTP session on the system i.

lcd dir_name

CoolSpools Installation Guide V6R1 www.ariadnesoftware.co.uk where dir_name is the name of the directory on your PC in which you unzipped the CP_INSTALL.SAV file earlier. This command makes dir_name the current directory of your FTP session on the PC.

put CP_INSTALL.SAV CP_INSTALL.FILE

This command transmits the contents of the file CP_INSTALL.SAV which was earlier unzipped from CP_INSTALL.ZIP to the save file called CP_INSTALL which you created earlier on your system i.

quit

This ends the FTP session.

e)

On your system i, ensure that the previous step worked by displaying the contents of save file CP_INSTALL

dspsavf CP_INSTALL/CP_INSTALL

If you see the message **(No records in save file)** then something has gone wrong during the preceding steps. Try following them again. If you still cannot get this procedure to work, contact us at <u>support@ariadnesoftware.co.uk.</u>

f)

On your system i, issue the following command to restore the CoolSpools installer to your system i:

RSTOBJ OBJ (*ALL) SAVLIB (CP_INSTALL) DEV (*SAVF) SAVF (CP_INSTALL/CP_INSTALL)

Now follow the instructions for running the CoolSpools installer on your system i as per <u>Method B</u> above.

The install library CP_INSTALL can be deleted once you have finished installing.

Method D

Manual installation on the system i

Summary

Select this method only if it is not possible to use any of the above methods for some reason as it is more complex than the others.

You are required to download one or more zip files each containing one or more system i save files. Those save files must be unzipped and transferred to the system i. You must then run a series of Restore Licensed Program (RSTLICPGM) commands to install the product options you want.

Note that CoolSpools does not need a PC and after installation all CoolSpools functionality runs entirely on the system i.

Prerequisites

- a) You must sign on to the system i as a user with *SECADM and *ALLOBJ special authorities.
- b) You must be able to use FTP to transfer data between your PC and the system i

Downloads

Refer to the table below for details of the files you can download and their contents.

Zip file name	Save file(s) included	Description
COOLSPV6R1.ZIP	CPV6R1BASE.SAV CPV6R1OPT1.SAV CPV6R1OPT2.SAV CPV6R1OPT3.SAV CPV6R1OPT4.SAV CPV6R1OPT5.SAV	Save files for the base product option and each individual product option (see below for details).
CPV6R1BASE.ZIP	CPV6R1BASE.SAV	Save file containing the CoolSpools Base option.
CPV6R1OPT1.ZIP	CPV6R1OPT1.SAV	Save file containing CoolSpools product option 1 (Spool Converter).
CPV6R1OPT2.ZIP	CPV6R1OPT2.SAV	Save file containing CoolSpools product option 2 (Email).
CPV6R1OPT3.ZIP	CPV6R1OPT3.SAV	Save file containing CoolSpools product option 3 (Spooled File

		Administration).
CPV6R1OPT4.ZIP	CPV6R1OPT4.SAV	Save file containing CoolSpools product option 4 (Database).
CPV6R1OPT5.ZIP	CPV6R1OPT5.SAV	Save file containing CoolSpools product option 5 (NetServer Toolkit).

The Base Option must be installed first. You will therefore need

either (a) COOLSPV6R1.ZIP (which contains all options)

or (b) CPV6R1BASE.ZIP (which contains the base option)

and the relevant product option ZIP files for the options you wish to install.

The instructions for each option are the same, but make sure you install the Base Option first.

Instructions

Repeat instructions a-f below for each product option. Do not repeat any step until you have completed all of the steps a-f for a particular product option (i.e. carry out steps a-f for the base option, then a-f for option 1, then a-f for option 2 etc.)

Alternatively, if you are able to install from the system i, you can just follow the procedure below for the base option and then use the "Install product options" option from the Base Option Menu. Display the base option menu by running:

GO COOLSPV6R1/BASEMENU

The zip files you download contain one or more save files as shown in the table above. The contents of these files must be transferred to a save file on the system i using FTP.

Transferring save files using FTP

This method uses FTP (File Transfer Protocol) to transfer the save file from your PC to your system i. It is assumed that you have stored the zip file(s) which you downloaded from the Internet on your PC and that you have enabled an FTP link between your PC and your system i.

Steps to be carried out on the PC are shown in green.

Steps to be carried out on the system i are shown in blue.

a)

On your PC, choose an existing directory or create a new directory for CoolSpools installation, either within Computer (My Computer, Windows Explorer), or from the DOS prompt, e.g.:

md c:\CoolSpools

CoolSpools Installation Guide V6R1 www.ariadnesoftware.co.uk

b)

On your PC, use WinZip. PKZIP etc. to extract the save file from the zip file into the directory you created in (a) above.

Alternatively, open the zip file as a directory in Computer (My Computer, Windows Explorer) and copy the CP_INSTALL.SAV file to the directory you created in (a) above.

c)

On your system i, create a library called CP_INSTALL, e.g.

crtlib CP INSTALL

then create a save file called CP_INSTALL in that library:

crtsavf CP INSTALL/CP INSTALL

d)

On your PC, start an FTP session to your system i. You may use FTP packages such as CuteFTP or simply go to the DOS prompt and type:

ftp AS400_name

where AS400_name is the name of your system i. You can also use the IP address rather than the system name.

You will be prompted to enter your user id and password. Please ensure that you sign on with a user id that has adequate authority. We recommend that you sign on as the Security Officer QSECOFR or another user profile with *SECADM and *ALLOBJ special authorities.

Issue the following FTP commands within the FTP session:

bin

This command instructs FTP not to carry out any conversion on the data to be sent to the system i.

quote site na 1

This makes sure the system i is using naming format 1 (path naming). This is important if your FTP attributes (CHGFTPA command NAMEFMT parameter) have the initial naming format set to *LIB (library/object naming) rather than *PATH (IFS path naming).

cd /QSYS.LIB/CP INSTALL.LIB

This command makes CP_INSTALL the current library of the FTP session on the system i.

lcd dir_name

where dir_name is the name of the directory on your PC in which you unzipped the save file in (b) above. This command makes dir_name the current directory of your FTP session on the PC.

put save_file_name.SAV CP_INSTALL.FILE

where **save_file_name.SAV** is the name of the save file you unzipped in (b) above. This command transmits the contents of the file you unzipped on your PC to the save file called CP_INSTALL which you created earlier on your system i.

quit

This ends the FTP session.

e)

On your system i, ensure that the previous step worked by displaying the contents of save file CP_INSTALL

dspsavf CP_INSTALL/CP_INSTALL

If you see the message **(No records in save file)** then something has gone wrong during the preceding steps. Try following them again. If you still cannot get this procedure to work, contact us at support@ariadnesoftware.co.uk.

f)

On your system i, issue the following command to restore the licensed program option:

```
rstlicpgm licpgm(6COOLSP)
dev(*savf)
option(option_number)
rstobj(*all)
lng(*primary)
output(*none)
rls(*first)
replacerls(*only)
savf(CP_INSTALL/CP_INSTALL)
```

where *option_number* is *BASE for the base option or 1, 2, 3, 4 or 5 for product options 1-5.

You will be asked to confirm your acceptance of the license agreement by pressing F14 after you have had an opportunity to review its contents on-screen.